

## Message Logging Reference

# Novell® ZENworks® 10 Configuration Management

**10.1**

August 6, 2008

[www.novell.com](http://www.novell.com)



## Legal Notices

Novell, Inc., makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc., makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2008 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc., has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the [Novell Legal Patents Web page \(http://www.novell.com/company/legal/patents/\)](http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc.  
404 Wyman Street, Suite 500  
Waltham, MA 02451  
U.S.A.  
[www.novell.com](http://www.novell.com)

*Online Documentation:* To access the latest online documentation for this and other Novell products, see the [Novell Documentation Web page \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

## **Novell Trademarks**

For Novell trademarks, see [the Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

## **Third-Party Materials**

All third-party trademarks are the property of their respective owners.



# Contents

<b>About This Guide</b>	<b>7</b>
<b>1 Overview</b>	<b>9</b>
1.1 Functionalities of Message Logger	9
1.2 Message Severity	9
1.3 Message Format	10
<b>2 Configuring Message Logger Settings</b>	<b>11</b>
2.1 Configuring the Message Logger Settings at the Zone Level	11
2.1.1 Local Device Logging	11
2.1.2 Centralized Message Logging	12
2.2 Configuring the Message Logger Settings at the Folder Level	15
2.3 Configuring the Message Logger Settings at the Device Level	15
2.4 Turning on the Debug Messages	15
<b>3 Managing Messages</b>	<b>17</b>
3.1 Understanding Message Formats	17
3.1.1 Local Log File Format	17
3.1.2 E-Mail Format	18
3.1.3 SNMP Message Format	18
3.1.4 UDP Payload Format	19
3.2 Viewing the Message Status	20
3.2.1 Message Summary	20
3.2.2 Device Hot List	20
3.3 Viewing the Messages	21
3.3.1 Message Log	21
3.3.2 System Message Log	22
3.4 Acknowledging Messages	22
3.4.1 Acknowledging a Message	23
3.4.2 Acknowledging Multiple Messages	23
3.4.3 Acknowledging Messages Logged During a Specified Time	24
3.5 Deleting Messages	24
3.5.1 Deleting a Message	24
3.5.2 Deleting Multiple Messages	25
3.5.3 Deleting Messages Logged During a Specified Time	25



# About This Guide

This *Novell ZENworks 10 Configuration Management Message Logging Reference* includes information about Message Logger features and procedures to help you configure and maintain your Novell® ZENworks® system. The information in this guide is organized as follows:

- ♦ Chapter 1, “Overview,” on page 9
- ♦ Chapter 2, “Configuring Message Logger Settings,” on page 11
- ♦ Chapter 3, “Managing Messages,” on page 17

## Audience

This guide is intended for ZENworks administrators.

## Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to the [Novell Documentation Feedback site \(http://www.novell.com/documentation/feedback.html\)](http://www.novell.com/documentation/feedback.html) and enter your comments there.

## Additional Documentation

ZENworks 10 Configuration Management is supported by other documentation (in both PDF and HTML formats) that you can use to learn about and implement the product. For additional documentation, see the [ZENworks 10 Configuration Management with SP1 \(10.1\) documentation \(http://www.novell.com/documentation/zcm10/index.html\)](http://www.novell.com/documentation/zcm10/index.html).

## Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol (®, ™, etc.) denotes a Novell trademark. An asterisk (\*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux\*, should use forward slashes as required by your software.





The Message Logger component of Novell® ZENworks® 10 Configuration Management lets the other ZENworks components such as zenloader and webservices, ZENworks Management Daemon (ZMD), Remote Management, and Policy Enforcers log messages to different output targets. The output targets includes the system log, local log, database, SMTP, SNMP trap, and UDP.

The following sections provide additional information on the Message Logger component:

- [Section 1.1, “Functionalities of Message Logger,” on page 9](#)
- [Section 1.2, “Message Severity,” on page 9](#)
- [Section 1.3, “Message Format,” on page 10](#)

## 1.1 Functionalities of Message Logger

Message Logger performs the following functions:

- Writes messages to local log files.
- Writes messages to a system log or event log.
- Writes messages to the Management console.
- Sends messages to the Management server.
- Sends messages as SMTP mail to SMTP servers from the Primary Server.
- Sends messages as SNMP traps to remote or local machines from the Primary Server.
- Sends messages as UDP packets to UDP destinations.
- Writes messages to the ZENworks database.
- Automatically purges database entries from the ZENworks database.
- Automatically acknowledges the messages in the ZENworks database.

## 1.2 Message Severity

A message is an event that is generated by different components and modules. These events can be exceptions such as errors, warnings, information to a user, or a debug statement to debug a module.

Messages are classified based on the following severity levels:

**Error:** Indicates that an action cannot be completed because of a user or system error. These messages are critical and require immediate attention from an administrator.

**Warning:** Indicates an exception condition. These messages might not be an error but can cause problems if not resolved. These messages do not require immediate attention from an administrator.

**Information:** Provides feedback about something that happened in the product or system that is important and informative for an administrator.

**Debug:** Provides debug information to troubleshoot and solve problems that might occur. The debug messages are stored only in the local file.

## 1.3 Message Format

Messages are logged in different formats depending on the output targets. For more information on message formats see, [Section 3.1, “Understanding Message Formats,” on page 17](#).

# Configuring Message Logger Settings

# 2

The following sections provide information on configuring the settings of the Message Logger component of Novell® ZENworks® 10 Configuration Management.

- ♦ [Section 2.1, “Configuring the Message Logger Settings at the Zone Level,” on page 11](#)
- ♦ [Section 2.2, “Configuring the Message Logger Settings at the Folder Level,” on page 15](#)
- ♦ [Section 2.3, “Configuring the Message Logger Settings at the Device Level,” on page 15](#)
- ♦ [Section 2.4, “Turning on the Debug Messages,” on page 15](#)

## 2.1 Configuring the Message Logger Settings at the Zone Level


The following sections contain information to help you configure the settings in the Management Zone to enable message logging:

- ♦ [Section 2.1.1, “Local Device Logging,” on page 11](#)
- ♦ [Section 2.1.2, “Centralized Message Logging,” on page 12](#)

### 2.1.1 Local Device Logging

In ZENworks Control Center, the Local Device Logging page lets you configure the message logging to a local drive and the system log file of the managed device.

- 1 In ZENworks Control Center, click *Configuration*.
- 2 In the Management Zone Settings panel, click *Device Management*, then click *Local Device Logging*.
- 3 Configure the following options in the Local File panel:  
**Log Message to a Local File if Severity Is:** Choose from one of the following:
  - ♦ **Error:** Stores messages with a severity of Error.
  - ♦ **Warning and Above:** Stores messages with a severity of Warning and Error.
  - ♦ **Information and Above:** Stores messages with a severity of Information, Warning, and Error.
  - ♦ **Debug and Above:** Stores messages with a severity of Debug, Information, Warning, and Error.

If you need to troubleshoot a ZENworks Adaptive Agent issue on an individual device, you can change the severity setting so that additional information is logged. On the device, double-click the  icon in the system tray, click *Logging* in the left navigation pane, then select an option from the *Log Messages if Severity Is* drop-down list.

**Rolling Based on Size:** Closes the current log file and starts a new file based on the file size:

- ♦ **Limit File Size to:** Specify the maximum size of the log file, in either kilobytes (KB) or megabytes (MB). The log file is closed after the size of the file reaches the specified limit and a new file is started.
- ♦ **Number of Backup Files:** Specify the number of closed files to be backed up. The maximum number of backup files is 13.

**Rolling Based on Date:** Closes the current log file and starts a new file based on the following schedules:

- ♦ **Daily Pattern:** Starts a new file daily.
- ♦ **Monthly Pattern:** Starts a new file monthly.

On a Windows\* managed device, the local files are `zmd-messages.log`, `loader-messages.log`, and `services-messages.log`. The `zmd-messages.log` file is located in `\novell\zenworks\logs\localstore`. The `loader-messages.log` and `services-messages.log` are located in `\novell\zenworks\logs`.

On a Linux managed device, the local files `messages.log` and `services-messages.log` are located in `/var/opt/novell/log/zenworks`.

#### 4 Configure the following options in the System Log panel.

**Send Message to Local System Log if Severity Is:** Choose from one of the following:

- ♦ **Error:** Stores messages with severity of Error.
- ♦ **Warning and Above:** Stores messages with a severity of Warning and Error.
- ♦ **Information and Above:** Stores messages with a severity of Information, Warning, and Error.

The system log file is `event.log` on Windows and is `/var/log/messages` on Linux.

## 2.1.2 Centralized Message Logging

In ZENworks Control Center, the Centralized Message Logging page lets you configure the settings related to message logging performed by the Primary Server.

- 1 In ZENworks Control Center, click *Configuration*.
- 2 In the Management Zone Settings panel, click *Event and Messaging*, then click *Centralized Message Logging*.
- 3 In the Automatic Message Cleanup panel, configure the settings to automatically acknowledge or remove the logged messages from the ZENworks server:

**Preferred Maintenance Server:** Specify the IP address of the preferred server on which the Message Cleanup actions runs to acknowledge or delete the logged messages from database.

**Information:** Allows you to configure the following settings for the informational messages:

- ♦ **Auto acknowledge when older than [ ] days:** Allows you to automatically acknowledge the logged informational messages that are older than the number of days you specify. For example, if you specify 30 days, then all the informational messages logged before 30 days from the current date are acknowledged when the Message Cleanup activity is

scheduled to run. If you specify zero, then the informational messages dated until today are acknowledged. By default, all the informational messages older than 60 days are automatically acknowledged.

- ♦ **Auto delete when older than [ ] days:** Allows you to automatically delete the logged informational messages that are older than the number of days you specify. For example, if you specify 30 days, then all the informational messages logged before 30 days from the current date are deleted when the Message Cleanup activity is scheduled to run. If you specify zero, then the informational messages dated until today are deleted. By default, all the informational messages older than 60 days are automatically deleted.

If you want to specify both the auto-acknowledge and auto-delete days, then the number of auto-acknowledge days should always be less than the number for auto-delete days.

**Warnings:** Allows you to configure the following settings for the warning messages:

- ♦ **Auto acknowledge when older than [ ] days:** Allows you to automatically acknowledge the logged warning messages that are older than the number of days you specify. For example, if you specify 30 days, then all the warning messages logged before 30 days from the current date are acknowledged when the Message Cleanup activity is scheduled to run. If you specify zero, then the warning messages dated until today are acknowledged. By default, all the warning messages older than 60 days are automatically acknowledged.
- ♦ **Auto delete when older than [ ] days:** Allows you to automatically delete the logged warning messages that are older than the number of days you specify. For example, if you specify 30 days, then all the warning messages logged before 30 days from the current date are deleted when the Message Cleanup activity is scheduled to run. If you specify zero, then the warning messages dated until today are deleted. By default, all the warning messages older than 60 days are automatically deleted.

If you want to specify both the auto-acknowledge and auto-delete days, then the number of auto-acknowledge days should always be less than the number for auto-delete days.

**Errors:** Allows you to configure the following settings for the error messages:

- ♦ **Auto acknowledge when older than [ ] days:** Allows you to automatically acknowledge the logged error messages that are older than the number of days you specify. For example, if you specify 30 days, then all the error messages logged before 30 days from the current date are acknowledged when the Message Cleanup activity is scheduled to run. If you specify zero, then the error messages dated until today are acknowledged. By default, all the error messages older than 60 days are automatically acknowledged.
- ♦ **Auto delete when older than [ ] days:** Allows you to automatically delete the logged error messages that are older than the number of days you specify. For example, if you specify 30 days, then all the error messages logged before 30 days from the current date are deleted when the Message Cleanup activity is scheduled to run. If you specify zero, then error messages dated until today are deleted. By default, all the error messages older than 60 days are automatically deleted.

If you want to specify both the auto-acknowledge and auto-delete days, then the number of auto-acknowledge days should always be less than the number for auto-delete days.

**Select the Days of the Week and the Time to Perform the Message Cleanup:** Allows you to specify the time and the days of the week to run the Message Cleanup action. The administrator can set a daily schedule for Message Cleanup action.

**Use Coordinated Universal Time:** Allows you to convert the specified time to UTC (GMT) time. By default, this option is selected.

- 4** In the E-mail Notification panel, configure the settings to send the error messages to the administrators through e-mail:
- Send Log Message via E-mail if Severity Is:** Allows you to select the severity of the message to trigger sending the log messages through e-mail.
- From:** Specify the sender's e-mail address.
- To:** Specify the e-mail address of the recipients. You can specify more than one e-mail address by separating them with commas.
- Subject:** Specify the subject to be included while sending the e-mail from the Primary Server. You can customize the *Subject* field with macro values. For more information on customizing the subject field, see [Section 3.1.2, “E-Mail Format,” on page 18](#).
- 5** In the SNMP Traps panel, configure the SNMP traps on the ZENworks Server to send log messages:
- Send as SNMP Trap if Severity Is:** Sends an SNMP trap if the logged message's severity is Error.
- Trap Target:** Specify the IP address or DNS name of the SNMP server.
- Port:** Specify the port number of the SNMP server configured for this operation. By default, the port number is 162.
- Community String:** Specify the community string of the SNMP trap that is to be sent.
- 6** In the UDP Forwarder panel, configure the settings to send logged messages through the UDP services. The following table contains information on the options available:
- Send Message via UDP:** Sends messages to the UDP destinations if the logged message's severity is Error.
- UDP Destinations:** You can perform the following tasks with the *Add*, *Edit*, and *Remove* options:
- ♦ **Add a Server**
    1. Click *Add* to display the Add UDP Destination Address dialog box.
    2. Specify the server name and the UDP port number configured for this operation.
    3. Click *OK*.
  - ♦ **Remove a Server**
    1. Select the check box next to the server (or servers).
    2. Click *Remove*.
  - ♦ **Edit Server Details**
    1. Select the check box next to the server.
    2. Click *Edit* to display the Edit UDP Destination dialog box.
    3. Modify the settings as desired, then click *OK*.

## 2.2 Configuring the Message Logger Settings at the Folder Level

By default, the Message Logger settings configured at the zone level are applied to all the managed devices. However, you can modify the Local Device Logging settings for all the devices within a folder:

- 1 In ZENworks Control Center, click *Devices*.
  - 2 Click the *Folder (Details)* option for which you want to configure the Message Logger settings.
  - 3 Click *Settings*, then click *Device Management > Local Device Logging*.
  - 4 Click *Override*.
  - 5 Edit the logging settings as required.
  - 6 To apply the changes, click *Apply*.
- or
- To revert to the Local Device Logging settings configured at the zone level, click *Revert*.
- 7 Click *OK*.

## 2.3 Configuring the Message Logger Settings at the Device Level

By default, the Message Logger settings configured at the zone level are applied to all the managed devices. However, you can modify the Local Device Logging settings for the managed device:

- 1 In ZENworks Control Center, click *Devices*.
  - 2 Click *Servers* or *Workstations* to display the list of managed devices.
  - 3 Click the device for which you want to configure the Message Logger settings.
  - 4 Click *Settings*, then click *Device Management > Local Device Logging*.
  - 5 Click *Override*.
  - 6 Edit the logging settings as required.
  - 7 To apply the changes click *Apply*.
- or
- To revert to the Local Device Logging settings configured at the zone level, click *Revert*.
- 8 Click *OK*.

## 2.4 Turning on the Debug Messages

To turn on the logging of debug messages for all components:

- 1 In ZENworks Control Center, click *Configuration*.
- 2 In the Management Zone Settings panel, click *Device Management*, then click *Local Device Logging*.
- 3 In the local file panel, select the *Log message to a local file if severity is* option, then select the severity as *Debug and above*.
- 4 Click *Apply*, then click *OK*.





# Managing Messages

# 3

The Message Logger component lets you manage the messages logged by the other components of Novell® ZENworks® 10 Configuration Management.

- ♦ [Section 3.1, “Understanding Message Formats,” on page 17](#)
- ♦ [Section 3.2, “Viewing the Message Status,” on page 20](#)
- ♦ [Section 3.3, “Viewing the Messages,” on page 21](#)
- ♦ [Section 3.4, “Acknowledging Messages,” on page 22](#)
- ♦ [Section 3.5, “Deleting Messages,” on page 24](#)

## 3.1 Understanding Message Formats

- ♦ [Section 3.1.1, “Local Log File Format,” on page 17](#)
- ♦ [Section 3.1.2, “E-Mail Format,” on page 18](#)
- ♦ [Section 3.1.3, “SNMP Message Format,” on page 18](#)
- ♦ [Section 3.1.4, “UDP Payload Format,” on page 19](#)

Messages are logged in different formats depending on the output targets such as local log, e-mail notification, SNMP traps, and UDP notification.

All error messages log the component name on which the error is generated. To troubleshoot the error, refer to the component’s Reference Guide.

**Example 1:** Error related to Policy Management.

```
[DEBUG] [7/22/2007 3:42:45 PM] [] [PolicyManager] [] [Name =  
RM_dev, Guid = 271414163524d000190dbc6fa94272aa, Type = remote  
management policy, Version = 2] [] [].
```

To troubleshoot this error, see the *ZENworks 10 Configuration Management Policy Management Reference*.

**Example 2:** Error related to Remote Management.

```
[ERROR] [15-07-2007 12:44:16] [] [Remote Management]  
[RemoteManagement.VNCEVENT_CANNOT_OPEN_EVENT] [Unable to open the  
<ZRMUserLoginEvent> event] [] [].
```

To troubleshoot this error, see the *ZENworks 10 Configuration Management Remote Management Reference*.

### 3.1.1 Local Log File Format

Messages are logged on the managed device and ZENworks Server in the following format:

```
[severity] [loggingTime] [userGUID] [componentName] [MessageID]  
[MessageString] [additionalInfo] [RelatedGUID].
```

For example, [DEBUG] [1/22/2007 12:09:15 PM] [] [ZMD] [] [refreshing QuickTaskRefresh(GeneralRefresh)] [] [].

### 3.1.2 E-Mail Format

An e-mail message consists of the message header and the message body:

- ♦ “Message Header” on page 18
- ♦ “Message Body” on page 18

#### Message Header

The subject field in the e-mail can be customized as required by using keyword substitution macros:

Macro	Value
%s	Severity of the message.
%c	Name of the component.
%d	ID of the device at which the message is generated.
%t	Time of the message generation.
%a	Alias name of the device where the message is generated.

For example, if you want the subject line to display as “ERROR occurred on device Testifies at 4/1/07 5:31:01 PM”, then specify “%s occurred on device %a at %t” in the *Subject* field.

#### Message Body

The message body consists of the following fields:

- ♦ **Device Alias:** Name of the device where the message is generated.
- ♦ **Device IP Address:** IP Address of the device where the message is generated.
- ♦ **Error:** [Date] Component name Message ID localized message string.
- ♦ **Additional Information:** (Optional) Any additional information.

### 3.1.3 SNMP Message Format

The SNMP messages consists of the following two parts:

- ♦ “SNMP Message Header” on page 18
- ♦ “Protocol Data Unit (PDU)” on page 19

#### SNMP Message Header

The following fields are contained in the header:

**Version Number:** Specifies the version of SNMP used. ZENworks 10 Configuration Management uses SNMPv1.

**Community String:** Defines an access environment for a group of network-management systems (NMS).

### Protocol Data Unit (PDU)

The following fields are contained in the PDU:

**Enterprise:** Identifies the type of managed object generating the trap. ZENworks 10 Configuration Management uses 1.3.6.1.4.1.23.2.80.100.

**Agent Address:** Provides the IP address of the machine where the trap was generated.

**Generic Trap Type:** Contains the integer value 6. Type 6 is an enterprise-specific trap type, which has no standard interpretation in SNMP. The interpretation of the trap depends upon the value in the specific trap type field, which is defined by the Message Logger MIB.

**Specific Trap Code:** For enterprise-specific traps generated by ZENworks 10 Configuration Management, the values in the specific trap type fields are as follows:

- ♦ For a severity level of MessageLogger.ERROR, the specific trap is 1.
- ♦ For a severity level of MessageLogger.WARN, the specific trap is 2.
- ♦ For a severity level of MessageLogger.INFO, the specific trap is 3.

**Time Stamp:** The time stamp indicating when the trap occurred.

**Variable Bindings:** Provides additional information pertaining to the trap. This field consists of the following name/value pairs:

- ♦ For trap ID 1.3.6.1.4.1.23.2.80.100.0.1, the value is the device GUID.
- ♦ For trap ID 1.3.6.1.4.1.23.2.80.100.0.2, the value is the device name.
- ♦ For trap ID 1.3.6.1.4.1.23.2.80.100.0.3, the value is the component name.
- ♦ For trap ID 1.3.6.1.4.1.23.2.80.100.0.4, the value is the time when the message was logged.
- ♦ For trap ID 1.3.6.1.4.1.23.2.80.100.0.5, the value is the message ID.
- ♦ For trap ID 1.3.6.1.4.1.23.2.80.100.0.6, the value is the probable cause.

### 3.1.4 UDP Payload Format

The payload is a byte array with null-terminated delimiters such as \0 or 0 x 00 (hexadecimal) for each element. Each element's data is presented as UTF-8 encoded strings and is explained below:

- ♦ The first element is the ZENworks version information. For example, 10.
- ♦ The second element is the value of severity of the message. The severity values are 4 for Informational, 6 for Warning, and 8 for Debug messages.
- ♦ The third element is the message date. The date is not locally specific and is represented as a UTF-8 string. For example, 09-Mar-2008 14:15:44.
- ♦ The fourth element is the user ID.
- ♦ The fifth element is the component name.
- ♦ The sixth element is the non-localized message ID.
- ♦ The seventh element is the localized message string.

- ♦ The eighth element is the additional information.
- ♦ The ninth element is the probable cause URL.
- ♦ The tenth element is the relatedGUID objects separated by commas.

---

**NOTE:** If the element does not have any data, it is represented as \0\0.

---

## 3.2 Viewing the Message Status

In ZENworks Control Center, you can view the status of the logged messages in the following panels on the home page.

- ♦ [Section 3.2.1, “Message Summary,” on page 20](#)
- ♦ [Section 3.2.2, “Device Hot List,” on page 20](#)




### 3.2.1 Message Summary

The Message Summary panel displays the number of critical, warning, and normal messages generated on the four main objects in the Management Zone namely: the servers, workstations, policies, and bundles.

**Figure 3-1** *Message Summary*

Message Summary				
				Total
 <a href="#">Servers</a>	<a href="#">3</a>	<a href="#">0</a>	<a href="#">5</a>	<a href="#">8</a>
 <a href="#">Workstations</a>	<a href="#">9</a>	<a href="#">1</a>	<a href="#">1</a>	<a href="#">11</a>
 <a href="#">Policies</a>	<a href="#">3</a>	<a href="#">0</a>	<a href="#">17</a>	<a href="#">20</a>
 <a href="#">Bundles</a>	<a href="#">2</a>	<a href="#">0</a>	<a href="#">5</a>	<a href="#">7</a>


In the Message Summary panel, you can do the following:


- ♦ Click an object type to display its root folder. For example, click *Servers* to display the Servers root folder.
- ♦ For any object type, click the number in one of its status columns (  ) to display a listing of all the objects that currently have that status. For example, to see the list of policies that have a normal status, click the number in the column of the *Policies*.
- ♦ For any object type, click the number in the *Total* column to display all of the objects of that type having critical, warning, or normal messages. For example, click the Total count for *Servers* to display a list of all servers having messages logged.

### 3.2.2 Device Hot List

The Device Hot List displays a list of the devices that have generated a critical or warning message. The device remains in the hot list until you acknowledge its message (or messages). You can use this list as a summary of problems that need attention on the device.

The list is ordered based on the severity of the events. To display the events, do one of the following:


- ♦ Click the  icon in the column heading to display only the events with a critical status.

- ♦ Click the  icon in the column heading to display only the events with a warning status.
- ♦ Click the device to display its message log.

To view the Device Hot List:

- 1 In ZENworks Control Center, click the *Home* tab.

Device Hot List					
			Type	Item	
3	45	22		<a href="#">blr-nrm-r6a</a>	
2	28	27		<a href="#">blr-nrm-r9a</a>	
2	25	23		<a href="#">blr-nrm-r5v2</a>	
2	0	0		<a href="#">blr-nrm-r3f</a>	
1	52	1		<a href="#">blr-nrm-r11d</a>	
1 - 5 of 15					
					show 5 items

The list displays only five items at a time. To display the next set of the items, click the  icon.

## 3.3 Viewing the Messages

In the ZENworks Control Center, you can view the logged messages as follows:

- ♦ [Section 3.3.1, “Message Log,” on page 21](#)
- ♦ [Section 3.3.2, “System Message Log,” on page 22](#)

### 3.3.1 Message Log






The Message Log displays all unacknowledged messages generated for the object, such as device, bundle, or policy.

To view the message logs:




- 1 In ZENworks Control Center, click the *Device Hot List* on the home page, then click the device to view its message log.

You can also use the *Devices* menu to view the logs:

- 1 In ZENworks Control Center, click *Devices*.
- 2 Click *Servers* or *Workstations* to display the list of managed devices.
- 3 Click the name of a device, then click the *Summary* tab to display:

Message Log			Advanced	
Status	Message	Date		
	<a href="#">The action local file rights policy (ID:local file rights policy</a>	3:20 AM		
	<a href="#">The drive "d:" is not a local fixed drive. Files/folders on this</a>	3:20 AM		
	<a href="#">The action local file rights policy (ID:local file rights policy</a>	3:14 AM		
	<a href="#">The drive "d:" is not a local fixed drive. Files/folders on this</a>	3:14 AM		
	<a href="#">The action grouppolicy (ID:grouppolicy) failed, but the action s</a>	3:11 AM		
1 - 5 of 91			show 5 items	

**Status:** Displays an icon indicating the type of message:

-  Critical Message
-  Warning
-  Normal

**Message:** Displays a brief description of the event that occurred.

**Date:** Displays the date and time the event occurred.











- 4 To view the log messages in the advanced view, click *Advanced* on the right corner of the Memory Log panel.

You can acknowledge or delete messages from the message log. For more information on acknowledging messages, see [Section 3.4, “Acknowledging Messages,” on page 22](#), and for information on deleting messages, see [Section 3.5, “Deleting Messages,” on page 24](#).




### 3.3.2 System Message Log

The System Message Log panel displays the unacknowledged messages generated by the ZENworks Servers and managed devices in the Management Zone.

- 1 In ZENworks Control Center, click *Configuration*.
- 2 Click *System Information* to display:

System Message Log				Advanced
Status	Message	Date	Source	
	<a href="#">POLICYHANDLERS.PrinterPolicy.LocalPrinterAddSuccess(http://164.9</a>	10:24 AM	 blr-nrm-r5v2	
	<a href="#">POLICYHANDLERS.PrinterPolicy.LocalPrinterAddSuccess(printerlocal)</a>	10:23 AM	 blr-nrm-r5v2	
	<a href="#">Printer \\164.99.154.214\share already exists for user , hence n</a>	10:23 AM	 blr-nrm-r5v2	
	<a href="#">The action printer_policy (ID:printer_policy) failed, but the ac</a>	10:23 AM	 blr-nrm-r5v2	
	<a href="#">IPrint client is already installed in the device, not reinstalli</a>	10:23 AM	 blr-nrm-r5v2	
1 - 5 of 820				show 5 items

**Status:** Displays an icon indicating the type of message:

-  Critical Message
-  Warning
-  Normal


**Message:** Displays a brief description of the event that occurred.

**Date:** Displays the date and time the event occurred.

- 3 To view the log messages in the advanced view, click *Advanced* on the right corner of the System Memory Log panel.

You can acknowledge or delete messages from the system message log. For more information on acknowledging messages, see [Section 3.4, “Acknowledging Messages,” on page 22](#), for information on deleting messages, see [Section 3.5, “Deleting Messages,” on page 24](#).

## 3.4 Acknowledging Messages


An acknowledged message is one that you have reviewed and marked as acknowledged ().

- ♦ [Section 3.4.1, “Acknowledging a Message,” on page 23](#)

- ♦ [Section 3.4.2, “Acknowledging Multiple Messages,” on page 23](#)
- ♦ [Section 3.4.3, “Acknowledging Messages Logged During a Specified Time,” on page 24](#)

### 3.4.1 Acknowledging a Message

- 1 In the Message Log panel or the System Message Log panel, click the message you want to acknowledge.
- 2 In the Message Detail Information dialog box, select the *Acknowledge* option, then click *OK*:



The acknowledged messages are removed from the Message Log panel or the System Message Log panel, depending on which panel you selected in [Step 1](#).

The acknowledged messages continue to be listed in the Advanced view of these logs, marked with a check mark (✓).

### 3.4.2 Acknowledging Multiple Messages


- 1 In the Message Log panel or the System Message Log panel, click *Advanced* on the right corner of the panel.
- 2 Select the messages to acknowledge, then click *Acknowledge*:

Acknowledge Delete				
<input type="checkbox"/>	Status	Message	Date	✓
<input type="checkbox"/>		<a href="#">The action local file rights policy (ID:local file rights policy)</a>	7/31/07 5:20:32 AM	✓
<input type="checkbox"/>		<a href="#">The drive "d:" is not a local fixed drive. Files/folders on this</a>	7/31/07 5:20:31 AM	✓
<input type="checkbox"/>		<a href="#">The action local file rights policy (ID:local file rights policy)</a>	7/31/07 3:20:13 AM	
<input type="checkbox"/>		<a href="#">The drive "d:" is not a local fixed drive. Files/folders on this</a>	7/31/07 3:20:12 AM	
<input type="checkbox"/>		<a href="#">The action local file rights policy (ID:local file rights policy)</a>	7/31/07 3:14:39 AM	
1 - 5 of 93 show 5 items				

The acknowledged messages are marked with a check mark (✓).

### 3.4.3 Acknowledging Messages Logged During a Specified Time

- 1 In ZENworks Control Center, click *Configuration*.
- 2 In the *Configuration Tasks*, click *Message Cleanup* to display:



- 3 In the Message Cleanup dialog box, select *Acknowledge*.
- 4 In the *Date Range* option, select the *Beginning Date* and the *Ending Date*.
- 5 Select the *Filter* option:  
**None:** Cleans up the messages in selected date range from all the devices.  
**Device:** Cleans up the messages in selected date range from the selected device.
- 6 Click *OK*.

A message cleanup action is initiated and a system message is logged after the cleanup action is completed. For more information on viewing system logs, see [Section 3.3.2, “System Message Log,” on page 22](#).

## 3.5 Deleting Messages

Deleting a message completely removes the message from your ZENworks system.

- ♦ [Section 3.5.1, “Deleting a Message,” on page 24](#)
- ♦ [Section 3.5.2, “Deleting Multiple Messages,” on page 25](#)
- ♦ [Section 3.5.3, “Deleting Messages Logged During a Specified Time,” on page 25](#)

### 3.5.1 Deleting a Message

- 1 In the Message Log panel or the System Message Log panel, click the message you want to delete.
- 2 In the Message Detail Information dialog box, select the *Delete* option, then click *OK*:



**Message Detail Information**

**Full Message:** The action local file rights policy (ID:local file rights policy) failed, but the action set is set to continue on failure.

**Additional Information:** None

**Severity:** Warning

**Date:** July 31, 2007 3:20:13 AM

**Acknowledged Date:** None

**Source:** /Devices/Workstations/blr-nrm-r6a

**Message ID:** ActionMan.ActionContinueOnFailure

**Probable Cause URL:** None

**Log ID:** 69dc3fe71d570f2ea00297150cf23d99

**Related Objects:** None






☐ Acknowledge

☐ Delete

<< Previous Message    Next Message >>    OK    Cancel

## 3.5.2 Deleting Multiple Messages


- 1 In the Message Log panel or the System Message Log panel, click *Advanced* on the right corner of the panel.

Acknowledge		Delete	
<input type="checkbox"/> Status	Message	Date	✓
<input type="checkbox"/>	 <a href="#">The action local file rights policy (ID:local file rights policy)</a>	7/31/07 5:20:32 AM	✓
<input type="checkbox"/>	 <a href="#">The drive "d:" is not a local fixed drive. Files/folders on this</a>	7/31/07 5:20:31 AM	✓
<input type="checkbox"/>	 <a href="#">The action local file rights policy (ID:local file rights policy)</a>	7/31/07 3:20:13 AM	
<input type="checkbox"/>	 <a href="#">The drive "d:" is not a local fixed drive. Files/folders on this</a>	7/31/07 3:20:12 AM	
<input type="checkbox"/>	 <a href="#">The action local file rights policy (ID:local file rights policy)</a>	7/31/07 3:14:39 AM	
1 - 5 of 93		show 5 items	

- 2 Select the messages to delete, then click *Delete*.

## 3.5.3 Deleting Messages Logged During a Specified Time

- 1 In ZENworks Control Center, click *Configuration*.
- 2 In the *Configuration Tasks*, click *Message Cleanup*.



- 3 In the Message Cleanup dialog box, select *Permanently Delete*.
- 4 In the *Date Range* option, select the *Beginning Date* and the *Ending Date*.
- 5 Select the *Filter* option:
  - None:** Cleans up the messages in selected date range from all the devices.
  - Device:** Cleans up the messages in selected date range from the selected device.
- 6 Click *OK*.
- 7 In the Confirm Delete Dialog box, click *OK* to delete the message.

A system message is logged after the cleanup action is completed. For more information on viewing the system log see, [Section 3.3.2, “System Message Log,” on page 22](#).