

Administration Quick Start

Novell® ZENworks® 10 Asset Management SP2

10.2

May 27, 2009

www.novell.com



Legal Notices

Novell, Inc., makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc., makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2007-2009 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc., has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the [Novell Legal Patents Web page \(http://www.novell.com/company/legal/patents/\)](http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc.
404 Wyman Street, Suite 500
Waltham, MA 02451
U.S.A.
www.novell.com

Online Documentation: To access the latest online documentation for this and other Novell products, see the [Novell Documentation Web page \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

Novell Trademarks

For Novell trademarks, see [the Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

About This Guide	7
1 Administration Quick List	9
1.1 Zone Configuration	9
1.2 ZENworks Adaptive Agent Deployment	10
1.3 Asset Management	11
1.4 System Messages and Reports	11
2 Management Tools Quick View	13
2.1 ZENworks Control Center	13
2.1.1 Accessing ZENworks Control Center	13
2.1.2 Navigating ZENworks Control Center	14
2.2 zman Command Line Utility	15
2.2.1 Location	15
2.2.2 Syntax	15
2.2.3 Help with Commands	15
2.3 zac Command Line Utility	16
2.3.1 Location	16
2.3.2 Syntax	16
2.3.3 Help with Commands	16
3 Zone Configuration	19
3.1 Organizing Devices: Folders and Groups	19
3.1.1 Folders	19
3.1.2 Groups	21
3.2 Registering Devices	23
3.2.1 Registration Keys	24
3.2.2 Registration Rules	25
3.2.3 Device Naming Template	27
3.2.4 Where to Find More Information	27
3.3 Connecting to User Sources	27
3.4 Creating ZENworks Administrator Accounts	29
3.5 Modifying Configuration Settings	32
3.5.1 Modifying Configuration Settings at the Zone	32
3.5.2 Modifying Configuration Settings on a Folder	33
3.5.3 Modifying Configuration Settings on a Device	33
4 ZENworks Adaptive Agent Deployment	35
4.1 Discovering Network Devices	35
4.2 Importing Devices	36
4.3 Installing the ZENworks Adaptive Agent	37
4.3.1 Manual Installation	37
4.3.2 ZENworks Control Center Deployment Task	38

5	Asset Management	45
5.1	Collecting Software and Hardware Inventory	45
5.1.1	Initiating a Device Scan	46
5.1.2	Viewing a Device Inventory	46
5.1.3	Generating an Inventory Report	47
5.1.4	Where to Find More Information	48
5.2	Monitoring Software Usage	48
5.3	Monitoring License Compliance	49
5.3.1	Recording Software Purchases	51
5.3.2	Creating Licensed Products	53
5.3.3	Viewing Compliance Data	55
6	Device Retirement	57
6.1	Retiring a Managed Device	57
6.2	Retiring an Inventoried-Only Device	57
7	System Messages and Reports	59
7.1	Viewing System Messages	59
7.1.1	Viewing a Summary of Messages	59
7.1.2	Acknowledging Messages	60
7.1.3	Where to Find More Information	61
7.2	Creating a Watch List	61
7.3	Generating Reports	62

About This Guide

This *ZENworks 10 Asset Management Administration Quick Start* helps you quickly master the basics of administering your ZENworks® system. You should already have installed your ZENworks system. If not, see the *ZENworks 10 Asset Management Installation Guide*.

The information in this guide is organized as follows:

- ♦ **Administration Quick List (page 9)**: Provides a check list of what you need to do to configure and monitor your ZENworks system, deploy the ZENworks Adaptive Agent to devices you want to manage, and then perform management tasks on the devices.
- ♦ **Management Tools Quick View (page 13)**: Introduces ZENworks Control Center and the zman command line utility, the two primary ZENworks management tools.
- ♦ **Zone Configuration (page 19)**: Provides instructions for configuring your ZENworks system to best support the management tasks you'll perform.
- ♦ **ZENworks Adaptive Agent Deployment (page 35)**: Provides instructions for installing the ZENworks Adaptive Agent to devices. The Adaptive Agent is required on any device you want to manage with ZENworks.
- ♦ **Asset Management (page 45)**: Provides instructions for performing software and hardware inventory of devices, monitoring software usage, and monitoring software license compliance.
- ♦ **Device Retirement (page 57)**: Provides instructions for retiring devices from your Management Zone.
- ♦ **System Messages and Reports (page 59)**: Introduces the ways you can get information about the activity in your ZENworks system.

Audience

This guide is intended for anyone who will configure the ZENworks system, monitor the ZENworks system, or perform any ZENworks tasks related to managing devices or users.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to the [Novell Documentation Feedback site \(http://www.novell.com/documentation/feedback.html\)](http://www.novell.com/documentation/feedback.html) and enter your comments there.

Additional Documentation

ZENworks 10 Asset Management is supported by other documentation (in both PDF and HTML formats) that you can use to learn about and implement the product. For additional documentation, see the [ZENworks 10 Asset Management documentation \(http://www.novell.com/documentation/zam10\)](http://www.novell.com/documentation/zam10).

Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol (® , ™, etc.) denotes a Novell trademark. An asterisk (*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux*, should use forward slashes as required by your software.

Administration Quick List

1



You've installed your ZENworks® Server (or maybe a couple of servers) and are eager to start using all of the time-saving functionality in Novell® ZENworks 10 Asset Management SP2. The following sections are designed to quickly introduce you to the configuration, deployment, management, and status monitoring concepts and tasks that help you effectively manage the devices in your environment.




- ♦ [Section 1.1, “Zone Configuration,” on page 9](#)
- ♦ [Section 1.2, “ZENworks Adaptive Agent Deployment,” on page 10](#)
- ♦ [Section 1.3, “Asset Management,” on page 11](#)
- ♦ [Section 1.4, “System Messages and Reports,” on page 11](#)

1.1 Zone Configuration

Before you start compiling software and hardware inventories for devices, tracking software usage on devices, and monitoring license compliance, there are a few configuration tasks you need to complete to ensure that your Management Zone is configured to let you take full advantage of ZENworks management capabilities.

Table 1-1 *Zone Configuration Tasks*



Task	Details
 Create folders and groups for organizing devices	<p>Organize devices into folders and groups to ease the overhead involved in applying ZENworks configuration settings and performing tasks on similar devices. Rather than making assignments or performing tasks on individual devices, you can manage the folders and groups, with each device in a folder or group inheriting the assignment or task.</p> <p>For instructions, see Section 3.1, “Organizing Devices: Folders and Groups,” on page 19.</p>
 Create registration keys or rules	<p>The ZENworks Adaptive Agent must be installed on each device that you want to manage. When you deploy the ZENworks Adaptive Agent to a device, the device is registered in your Management Zone.</p> <p>You can use registration keys or rules to automatically assign devices to the appropriate folders and groups, ensuring that they immediately receive the correct configuration settings assignments.</p> <p>For instructions, see Section 3.2, “Registering Devices,” on page 23.</p>


Task	Details
 Add user sources	<p>You can connect to one or more LDAP directories to provide authoritative user sources in ZENworks. Adding a user source lets you associate ZENworks administrator accounts with LDAP user accounts, associate devices with the users who primarily use them, and run asset inventory and management reports that include users.</p> <p>For instructions, see Section 3.3, “Connecting to User Sources,” on page 27.</p>
 Create additional administrator accounts	<p>During installation, a default ZENworks administrator account (named Administrator) is created. The default Administrator account provides rights to the entire Management Zone.</p> <p>You can create additional administrator accounts that restrict access to the zone. For example, you could create an account that only provides the ability to run license compliance reports.</p> <p>For instructions, see Section 3.4, “Creating ZENworks Administrator Accounts,” on page 29.</p>
 Modify zone configuration settings	<p>Your zone settings are preset to provide the most common configuration. If necessary, you can change the settings.</p> <p>For instructions, see Section 3.5, “Modifying Configuration Settings,” on page 32.</p>

1.2 ZENworks Adaptive Agent Deployment

The ZENworks Adaptive Agent communicates with the ZENworks Server to perform management tasks on a device. You must deploy the Adaptive Agent to all devices you want to manage. Deploying the Adaptive Agent installs the agent files and registers the device in your Management Zone.




Table 1-2 *Deployment Tasks*

Task	Details
 Discover devices	<p>If you choose to use ZENworks Control Center to deploy the agent to devices, you must first add the devices to your Management Zone. You can do this by performing a network discovery.</p> <p>For instructions, see Section 4.1, “Discovering Network Devices,” on page 35.</p>
 Import devices	<p>You can also import devices into your Management Zone from a comma-separated values (CSV) file. Each device entry must include its IP address or DNS name.</p> <p>For instructions, see Section 4.2, “Importing Devices,” on page 36.</p>

Task	Details
 Install the ZENworks Adaptive Agent	<p>You can use a variety of methods to install the ZENworks Adaptive Agent to a device:</p> <ul style="list-style-type: none"> ♦ Use ZENworks Control Center to deploy the agent from a ZENworks Server to the device. ♦ At the device, use a Web browser to download the agent from a ZENworks Server and install it. ♦ Include the agent in an image and apply the image to the device. <p>For instructions, see Section 4.3, “Installing the ZENworks Adaptive Agent,” on page 37.</p>

1.3 Asset Management




Table 1-3 *Asset Management*

Task	Details
 Scan devices to collect software and hardware inventory	<p>Scan devices to collect software and hardware inventories for the devices. The inventory information can help you make decisions about software distribution and hardware upgrades.</p> <p>For instructions, see Section 5.1, “Collecting Software and Hardware Inventory,” on page 45.</p>
 Monitor software usage	<p>Generate reports to analyze how much and how often software products are being used.</p> <p>For instructions, see Section 5.2, “Monitoring Software Usage,” on page 48.</p>
 Monitor software license compliance	<p>See whether your installed software products are properly licensed, under licensed, or over licensed.</p> <p>For instructions, see Section 5.3, “Monitoring License Compliance,” on page 49.</p>

1.4 System Messages and Reports

As you perform management tasks in your zone, information is recorded so that you can view the status of your zone and the activities taking place within it.

Table 1-4 *System Messages and Reports Tasks*

Task	Details
 View system messages.	<p>The ZENworks system generates informational, warning, and error messages to help you monitor activities such as the distribution of software and application of policies.</p> <p>For instructions, see Section 7.1, “Viewing System Messages,” on page 59.</p>
 Create a Watch List.	<p>If you have devices whose activity you want to closely monitor, you can add them to the Watch List.</p> <p>For instructions, see Section 7.2, “Creating a Watch List,” on page 61.</p>
 Generate reports.	<p>Generate reports for devices and much more.</p> <p>For instructions, see Section 7.3, “Generating Reports,” on page 62.</p>

Management Tools Quick View

2

Novell® ZENworks® 10 Asset Management provides both a Web-based console (ZENworks Control Center) and a command line utility (zman) that you can use to manage your ZENworks system. The following sections explain how to access and use the management tools:

- ♦ [Section 2.1, “ZENworks Control Center,” on page 13](#)
- ♦ [Section 2.2, “zman Command Line Utility,” on page 15](#)
- ♦ [Section 2.3, “zac Command Line Utility,” on page 16](#)

2.1 ZENworks Control Center

ZENworks Control Center is installed on all ZENworks Servers in the Management Zone. You can perform all management tasks on any ZENworks Server.

- ♦ [Section 2.1.1, “Accessing ZENworks Control Center,” on page 13](#)
- ♦ [Section 2.1.2, “Navigating ZENworks Control Center,” on page 14](#)


2.1.1 Accessing ZENworks Control Center

- 1 Using a Web browser that meets the requirements listed in “[Administration Browser Requirements](#)” in the *ZENworks 10 Asset Management Installation Guide*, enter the following URL:

`https://ZENworks_Server_Address:port`

Replace *ZENworks_Server_Address* with the IP address or DNS name of the ZENworks Server. You only need to specify the *port* if you are not using one of the default ports (80 or 443). ZENworks Control Center requires an HTTPS connection; HTTP requests are redirected to HTTPS.

The login dialog box is displayed.

The image shows a web-based login dialog box for Novell ZENworks. The title bar is orange and contains the text "Novell® ZENworks® Login" and a "Help" button. The main area is light gray and contains four input fields: "Management Zone:" with the value "DOC_20070601B", "Username:" (empty), "Password:" (empty), and "Language:" with a dropdown menu showing "English". A "Login" button is located at the bottom right of the input fields. At the bottom of the dialog box, there is a red "N" logo.

- 2 In the *Username* field, type Administrator.
- 3 In the *Password* field, type the Administrator password created during installation.

To prevent unauthorized users from gaining access to ZENworks Control Center, the administrator account is disabled after three unsuccessful login attempts, and a 60-second timeout is enforced before you can attempt another login. To change these default values, see “[Changing the Default Login Disable Values](#)” in the *ZENworks 10 Asset Management System Administration Reference*.


- 4 Click *Login* to display ZENworks Control Center.

For more detailed information on logging in as a different administrator, see “[Accessing ZENworks Control Center](#)” in the *ZENworks 10 Asset Management System Administration Reference*.

NOTE: If you use Novell iManager as the management tool for other Novell products, you can set up ZENworks Control Center to be available through iManager. For instructions, see “[Accessing ZENworks Control Center through Novell iManager](#)” in the *ZENworks 10 Asset Management System Administration Reference*.

2.1.2 Navigating ZENworks Control Center

The following Servers page represents a standard view in ZENworks Control Center.



Navigation Tabs: The tabs in the left pane let you navigate among the functional areas of ZENworks. For example, the Servers page shown above lets you manage tasks associated with servers.

Task List: The task list in the left pane provides quick access to the most commonly performed tasks for the current page. The task list changes for each page.

Frequently Used Objects: The Frequently Used list in the left pane displays the 10 objects that you have accessed most often, from most used to least used. Clicking an object takes you directly to the details page for the object.

Work Panel: The work panels are where you monitor and manage your ZENworks system. The panels change depending on the current page. In the above example, there are two work panels: *Devices* and *Search*. The *Devices* panel lists the servers, folders, server groups, and dynamic server groups that have been created; you use this panel to manage servers. The *Search* panel lets you filter the *Devices* panel based on criteria such as a server's name, operating system, or status.

Help Information: The Help button links to Help topics that provide information about the current page. The Help button links change depending on the current page.

2.2 zman Command Line Utility

The zman utility provides a command line management interface that lets you perform the tasks available in ZENworks Control Center.

The primary purpose of the zman utility is to enable you to perform operations through a script. However, you can also perform operations manually at a command line.

- [Section 2.2.1, “Location,” on page 15](#)
- [Section 2.2.2, “Syntax,” on page 15](#)
- [Section 2.2.3, “Help with Commands,” on page 15](#)

2.2.1 Location

The utility is installed on all ZENworks Servers in the following location:

```
%ZENWORKS_HOME%\bin
```

where %ZENWORKS_HOME% represents the ZENworks installation path. On Windows, the default path is c:\novell\zenworks\bin. On Linux*, the default path is opt/novell/zenworks/bin.

2.2.2 Syntax

The zman utility uses the following basic syntax:

```
zman category-action [options]
```

For example, to initiate an inventory scan of a device, you use the following command:

```
zman inventory-scan-now device/servers/server1
```

where `inventory-scan-now` is the category-action and `device/servers/server1` is an option that specifies the folder path of the device to be scanned.

2.2.3 Help with Commands

The best way to understand the commands is to use the online help or see “[zman\(1\)](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

To use the online help:

- 1 On the ZENworks Server, enter `zman --help` at a command prompt.

This command displays the basic usage (syntax) and a list of the available command categories. You can also use the following to get help:

Command	Description
<code>zman --help more</code>	Displays a complete list of commands by category.
<code>zman category --help more</code>	Displays a complete list of commands within a category.
<code>zman command --help more</code>	Displays help for a command

2.3 zac Command Line Utility

The zac utility provides a command line management interface that lets you perform tasks available in the ZENworks Adaptive Agent.

- [Section 2.3.1, “Location,” on page 16](#)
- [Section 2.3.2, “Syntax,” on page 16](#)
- [Section 2.3.3, “Help with Commands,” on page 16](#)

2.3.1 Location

The utility is installed on all Windows managed devices in the following location:

```
%ZENWORKS_HOME%\bin
```

where %ZENWORKS_HOME% represents the ZENworks installation path. The default path is `c:\novell\zenworks\bin`.

2.3.2 Syntax

The zac utility uses the following basic syntax:

```
zac command options
```

For example, to initiate an inventory scan on a device, you use the following command:

```
zac inv scannow
```

where `inv` is the command and `scannow` is the command option.

2.3.3 Help with Commands

The best way to understand the commands is to use the online help or see “[zac\(1\)](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

To use the online help:

- 1 On the managed device, enter one of the following commands at a command prompt.

Command	Description
<code>zac --help</code>	Displays a complete list of commands.

Command	Description
<code>zac command --help</code>	Displays detailed help for a command.

Novell® ZENworks® 10 Asset Management is designed to let you efficiently manage the software and hardware assets of a large number of devices with as little effort as possible. The first step in easing this management burden is to ensure that you've configured your Management Zone so that you can take full advantage of the ZENworks capabilities.

The following sections introduce the basic concepts you need to set up a Management Zone that best supports the ongoing management tasks you perform. Each section explains a management concept and provides general steps to perform the tasks associated with the concept.

- ♦ [Section 3.1, “Organizing Devices: Folders and Groups,” on page 19](#)
- ♦ [Section 3.2, “Registering Devices,” on page 23](#)
- ♦ [Section 3.3, “Connecting to User Sources,” on page 27](#)
- ♦ [Section 3.4, “Creating ZENworks Administrator Accounts,” on page 29](#)
- ♦ [Section 3.5, “Modifying Configuration Settings,” on page 32](#)

3.1 Organizing Devices: Folders and Groups

Using ZENworks Control Center, you can manage devices by performing tasks directly on individual device objects. However, this approach is not very efficient unless you have only a few devices to manage. To optimize management of a large number of devices, ZENworks lets you organize devices into folders and groups; you can then perform tasks on a folder or group to manage its devices.

You can create folders and groups at any time. However, the best practice is to create folders and groups before you register devices in your zone. This allows you to use registration keys and rules to automatically add devices to the appropriate folders and groups when they register (see [“Registering Devices” on page 23](#)).

- ♦ [Section 3.1.1, “Folders,” on page 19](#)
- ♦ [Section 3.1.2, “Groups,” on page 21](#)

3.1.1 Folders

Folders are a great tool to help you organize devices in order to simplify management of those devices. You can apply configuration settings and perform tasks on any folder. When you do so, the folder's devices inherit those settings and tasks.


For best results, you should place devices with similar configuration setting requirements in the same folder.

For example, assume that you have workstations at three different sites. You want to apply different configuration settings to the workstations at the three sites, so you create three folders (`/Workstations/Site1`, `/Workstations/Site2`, and `/Workstations/Site3`) and place the appropriate workstations in each folder. You decide that most of the configuration settings apply to all workstations, so you configure those settings at the Management Zone. However, you want to perform a weekly collection of software and hardware inventory at Site1 and Site2 and a monthly

inventory collection at Site3. You configure a weekly inventory collection at the Management Zone and then override the setting on the Site3 folder to apply a monthly schedule. Site1 and Site2 collect inventory weekly, and Site3 collects inventory monthly.

Creating a Folder

- 1 In ZENworks Control Center, click the *Devices* tab.
- 2 Click the *Workstations* folder.



- 3 Click *New > Folder* to display the New Folder dialog box.

The 'New Folder' dialog box is shown. It has three main input fields: 'Name:' (required), 'Folder:' (required, pre-filled with '/Devices/Workstations'), and 'Description:'. At the bottom, there are 'OK' and 'Cancel' buttons. A note at the bottom states: 'Fields marked with an asterisk are required.'

- 4 In the *Name* field, type a name for the new folder.

When you name an object in the ZENworks Control Center (folders, groups, and so forth), ensure that the name adheres to the following conventions:

- ♦ The name must be unique in the folder.

- ♦ Depending on the database software being used for the ZENworks database, uppercase and lowercase letters might not create uniqueness for the same name. The embedded database included with ZENworks Asset Management is case insensitive, so Folder 1 and FOLDER 1 are the same name and cannot be used in the same folder. If you use an external database that is case-sensitive, Folder 1 and FOLDER 1 are unique.
- ♦ If you use spaces, you must enclose the name in quotes when entering it on the command line. For example, you must enclose Folder 1 in quotes ("Folder 1") when entering it in the zman utility.
- ♦ The following characters are invalid and cannot be used: / \ * ? : " ' < > | ` % ~

5 Click *OK* to create the folder.

You can also use the `workstation-folder-create` and `server-folder-create` commands in the zman utility to create device folders. For more information, see “[Workstation Commands](#)” and “[Server Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

3.1.2 Groups

As you can with folders, you can also perform tasks on device groups. When you do so, the group’s devices inherit those tasks. Unlike with folders, you cannot apply configuration settings to groups.


Groups provide an additional layer of flexibility for tasks. In some cases, you might not want to perform the same task on all devices in a folder. Or, you might want to perform tasks on one or more devices in different folders. To do so, you can add the devices to a group (regardless of which folders contain the devices) and then perform the tasks on the group.

ZENworks provides both groups and dynamic groups. From the perspective of performing tasks, groups and dynamic groups function exactly the same. The only difference between the two types of groups is the way that devices are added to the group. With a group, you must manually add devices. With a dynamic group, you define criteria that a device must meet to be a member of the group, and then devices that meet the criteria are automatically added.

ZENworks include several predefined dynamic server groups (Windows 2000 Servers and Windows 2003 Servers) and dynamic workstation groups (Windows XP Workstation, Windows 2000 Workstation, and Windows Vista Workstations). Any devices that have these operating systems are automatically added to the appropriate dynamic group.

Creating a Group

- 1** In ZENworks Control Center, click the *Devices* tab.
- 2** If you want to create a group for servers, click the *Servers* folder.
or
If you want to create a group for workstations, click the *Workstations* folder.



- 3 Click *New > Server Group* (or *New > Workstation Group* for workstations) to launch the Create New Group Wizard.

Devices > Workstations > Create New Group

Create New Group

Step 1: Basic Information

Group Name: *

Folder: */Devices/Workstations

Description:

Fields marked with an asterisk are required.

<< Back Next >> Cancel

- 4 On the Basic Information page, type a name for the new group in the *Group Name* field, then click *Next*.
The group name must follow the **naming conventions**.
- 5 On the Summary page, click *Finish* to create the group without adding members.
or
Click *Next* if you want to add members to the group, then continue with **Step 6**.
- 6 On the Add Group Members page, click *Add* to add devices to the group, then click *Next* when finished adding devices.
- 7 On the Summary page, click *Finish* to create the group.


You can also use the `workstation-group-create` and `server-group-create` commands in the `zman` utility to create device groups. For more information, see “**Workstation Commands**” and “**Server Commands**” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

Creating a Dynamic Group

- 1 In ZENworks Control Center, click the *Devices* tab.
- 2 If you want to create a group for servers, click the *Servers* folder.

or

If you want to create a group for workstations, click the *Workstations* folder.



- 3 Click *New > Dynamic Server Group* (or *New > Dynamic Workstation Group* for workstations) to launch the Create New Group Wizard.

Group Name: *

Folder: *

Description:

<< Back Next >> Cancel

- 4 On the Basic Information page, type a name for the new group in the *Group Name* field, then click *Next*.

The group name must follow the **naming conventions**.

- 5 On the Define Filter for Group Members page, define the criteria that a device must meet to become a member of the group, then click *Next*.

Click the *Help* button for details about creating the criteria.

- 6 On the Summary page, click *Finish* to create the group.

3.2 Registering Devices

When you deploy the ZENworks Adaptive Agent to a device, the device is registered in your Management Zone and becomes a managed device. As part of the registration, you can specify the device's ZENworks name and the folder and groups to which you want the device added.

By default, a device's hostname is used as its ZENworks name, it is added to the /Servers or /Workstations folder, and it is not given membership in any groups. You can manually move devices to other folders and add them to groups, but this can be a burdensome task if you have a large number of devices or if you are consistently adding new devices. The best way to manage a large number of devices is to have them automatically added to the correct folders and groups during registration.

To add devices to folders and groups during registration, you can use registration keys, registration rules, or both. Both registration keys and registration rules let you assign folder and group memberships to a device. However, there are differences between keys and rules that you should be aware of before choosing whether you want to use one or both methods for registration.

- ♦ [Section 3.2.1, “Registration Keys,” on page 24](#)
- ♦ [Section 3.2.2, “Registration Rules,” on page 25](#)
- ♦ [Section 3.2.3, “Device Naming Template,” on page 27](#)
- ♦ [Section 3.2.4, “Where to Find More Information,” on page 27](#)


3.2.1 Registration Keys

A registration key is an alphanumeric string that you manually define or randomly generate. During deployment of the ZENworks Adaptive Agent on a device, the registration key must be provided. When the device connects to a ZENworks Server for the first time, the device is added to the folder and groups defined within the key.

You can create one or more registration keys to ensure that devices are placed in the desired folders and groups. For example, you might want to ensure that all of the Sales department's workstations are added to the /Workstations/Sales folder but are divided into three different groups (SalesTeam1, SalesTeam2, SalesTeam3) depending on their team assignments. You could create three different registration keys and configure each one to add the Sales workstations to the /Workstations/Sales folder and the appropriate team group. As long as each workstation uses the correct registration key, it is added to the appropriate folder and group.

To create a registration key:

- 1 In ZENworks Control Center, click the *Configuration* tab, then click the *Registration* tab.



- 2 In the Registration Keys panel, click *New > Registration Key* to launch the Create New Registration Key Wizard.


[Registration Keys](#) > [Create New Registration Key](#)

Create New Registration Key

Step 1: Basic Information

Supply the name, description, and the limit for the new registration key. A unique name can be generated by clicking on the "Generate unique key name" icon.

Name (used as the registration key code):

Folder: *
 

Description:

Number of times this key can be used:
☒ Unlimited
☐ Limit to:

- 3 Follow the prompts to create the key.

For information about what you need to supply at each step of the wizard, click the *Help* button.

You can also use the `registration-create-key` command in the `zman` utility to create a registration key. For more information, see “[Registration Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

3.2.2 Registration Rules

If you don’t want to enter a registration key during deployment, or if you want devices to be automatically added to different folders and groups based on predefined criteria (for example, operating system type, CPU, or IP address), you can use registration rules.

ZENworks includes a default registration rule for servers and another one for workstations. If a device registers without a key and you haven’t created registration rules, the default registration rules are applied to determine the folder assignments. The two default rules cause all servers to be added to the `/Servers` folder and all workstations to the `/Workstations` folder.

The two default rules are designed to ensure that no server or workstation registration fails. Therefore, you cannot delete or modify these two default rules. You can, however, define additional rules that enable you to filter devices as they register and add them to different folders and groups. If, as recommended in [Section 3.1, “Organizing Devices: Folders and Groups,” on page 19](#), you’ve established folders for devices with similar configuration settings and groups for devices on which you need to perform similar tasks, then newly registered devices automatically receive the appropriate configuration settings and tasks.

To create a registration rule:

- 1 In ZENworks Control Center, click the *Configuration* tab, then click the *Registration* tab.



- 2 In the Registration Rules panel, click *New* to launch the Create New Registration Rule Wizard.

[Registration Rules](#) > [Create New Rule](#)

Create New Rule

Step 1: Basic Information

Supply the name and description for the new Rule.

Name:

Description:

- 3 Follow the prompts to create the rule.

For information about what you need to supply at each step of the wizard, click the *Help* button.

You can also use the `ruleset-create` command in the `zman` utility to create a registration rule. For more information, see “[Ruleset Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

3.2.3 Device Naming Template

The device naming template determines how devices are named when they register. By default, a device's hostname is used. You can change it to use any combination of the following machine variables: `${HostName}`, `${GUID}`, `${OS}`, `${CPU}`, `${DNS}`, `${IPAddress}`.

- 1 In ZENworks Control Center, click the *Configuration* tab.
- 2 In the Management Zone Settings panel, click *Device Management*.
- 3 Click *Registration* to display the Registration page.

[Configuration](#) > **Registration**

Registration
Configure registration settings.

Device Naming Template
Name given to new machines:

Registration Rules
☒ Enable use of registration rules.
☒ Enable use of default registration rules.

Device Dynamic Rename
☐ Enable automatic renaming of devices.

OK Apply Reset Cancel

- 4 In the Device Naming Template panel, click , then select the desired machine variable from the list.

You can use any combination of one or more variables. For example:

`${HostName}${GUID}`

- 5 Click *OK* to save the changes.

3.2.4 Where to Find More Information

For more information about registering devices, see the *ZENworks 10 Discovery, Deployment, and Retirement Reference*.

3.3 Connecting to User Sources

You can connect to one or more LDAP directories to provide authoritative user sources in ZENworks. Adding a user source lets you associate ZENworks administrator accounts with LDAP user accounts, associate devices with the users who primarily use them, and run asset inventory and management reports that include users.

Your LDAP directory is not affected; ZENworks requires only read access to the LDAP directory. For more detailed information about the specific read rights required when connecting to a user source, see the *ZENworks 10 Asset Management System Administration Reference*.


You can connect to Novell eDirectory™ and Microsoft* Active Directory* as user sources. The minimum requirements are Novell eDirectory 8.7.3 and Microsoft Active Directory on Windows 2000 SP4. The minimum LDAP requirement is version 3.

After you connect to an LDAP directory, you define the containers within the directory that you want exposed. For example, assume you have a Microsoft Active Directory domain tree named MyCompany. All users reside in two containers in the MyCompany tree: MyCompany/Users and MyCompany/Temp/Users. You could reference the MyCompany tree as the source and the MyCompany/Users and MyCompany/Temp/Users as separate user containers. This limits access within the directory to only those containers that include users.

In addition to the users that reside within the containers you add, ZENworks Control Center also displays any user groups located in the containers. This enables management of both individual user and groups of users

To connect to a user source:


- 1 In ZENworks Control Center, click the *Configuration* tab.



- 2 In the User Sources panel, click *New* to launch the Create New User Source Wizard.

[User Sources](#) > **New User Source**


Create New User Source

 **Step 1: Connection Information**

Configuring a user source, allows Bundle and Policy objects to be assigned to identities contained in an LDAP directory. Please enter the connection information for the LDAP directory.

Address:

☒ Use SSL

Port: 

Root LDAP Context:
 (optional)
(e.g. dc=company,dc=com)

3 Follow the prompts to create the user source.

For information about what you need to supply at each step of the wizard, click the *Help* button.

You can also use the `user-source-create` command in the `zman` utility to create a connection to a user source. For more information, see “[User Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

3.4 Creating ZENworks Administrator Accounts

During installation, a default ZENworks administrator account (named Administrator) is created. This account, called a Super Administrator account, provides full administrative rights to the Management Zone.

Typically, you should create administrator accounts for each person who will perform administrative tasks. You can define these accounts as Super Administrator accounts, or you can define them as administrator accounts with restricted rights. For example, you could give a user an administrator account that only enables him or her to discover and register devices in the Management Zone. Or, the account might be limited to performing asset management tasks such as contract, license, and document management.

In some cases, you might have multiple administrator accounts that require the same administrative rights. Rather than assign rights to each account individually, you can create an administrator role, assign the administrative rights to the role, and then add the accounts to the role. For example, you might have a Help Desk role that provides administrative rights required by several of your administrators.

To create additional administrator accounts:

- 1** In ZENworks Control Center, click the *Configuration* tab.

Configuration	Registration	System Information	Asset Inventory	Asset Management	System Updates						
Management Zone Settings											
Content											
Device Management											
Discovery and Deployment											
Event and Messaging											
Infrastructure Management											
Inventory											
Reporting Services											
Asset Management											
Patch Management Services											
Server Hierarchy											
Administrators											
New Edit Delete											
<table border="1"> <thead> <tr> <th>Name</th> <th>Full Name</th> <th>Username in User Source</th> </tr> </thead> <tbody> <tr> <td colspan="3">No items available.</td> </tr> </tbody> </table>						Name	Full Name	Username in User Source	No items available.		
Name	Full Name	Username in User Source									
No items available.											
Roles											

- In the Administrators panel, click *New* to display the Add New Administrator dialog box.

Add new Administrator

There are two ways to create an Administrator:

☒ Create a new Administrator providing name and password.

Administrator Name:

Full Name:

Password:

Retype Password:

☐ Based on user(s) in a user source
will use the same credential defined in Authoritative source.

Add Remove

Name	In Folder
No items selected, click add to select items	

☐ Give this Administrator the same rights as I have.

Fields marked with an asterisk are required.

OK

Cancel

- Fill in the fields.

The Add New Administrator dialog box lets you create a new administrator account by providing a name and password, or you can create a new administrator based on an existing user in the user source. Optionally, you can give the new administrator the same rights that the logged-in administrator has.

Create a New Administrator by Providing Name, Password: Select this option if you want to create a new administrator account by manually specifying the name and password.

Based on User(s) in a User Source: Select this option if you want to create a new administrator account based on user information from your user source. To do so, click *Add*, then browse for and select the user you want.

Give this Administrator the Same Rights as I Have: Select this option to assign the new administrator the same rights that you have as the currently logged-in administrator.

- 4 When you have finished filling in the fields, click *OK* to add the new administrator to the Administrators panel.
- 5 If you need to change the new administrator's rights or roles, click the administrator account to display the account details:

[Configuration](#) > Admin1

General

Administrator Full Name:

☒ Super Administrator

Note: If the Super Administrator check box is checked, then this Administrator is a Super Administrator with all rights. This will override any assigned rights that may be allowed, denied, or not set.

Assigned Rights

[Add](#) [Edit](#) [Delete](#)

<input type="checkbox"/>	Type	Context	Rights
<small>No items available.</small>			

Note: Every admin receives view rights and they are not removable.

Assigned Roles

[Add](#) [Edit](#) [Delete](#)

<input type="checkbox"/>	Role	Type	Context
<small>No items available.</small>			

- 6 Using the Assigned Rights panel, modify the assigned rights.

For information about the options on the page, click the *Help* button, or see “[Managing Administrator Rights](#)” in the *ZENworks 10 Asset Management System Administration Reference*.

- 7 When you have finished modifying the rights, click *Apply* to save the changes.

For more information about creating ZENworks administrator accounts or administrator roles, see “[Administrators](#)” in the *ZENworks 10 Asset Management System Administration Reference*.

You can also use the `admin-create` command in the `zman` utility to create a ZENworks administrator account. For more information, see “[Administrator Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

3.5 Modifying Configuration Settings

The Management Zone configuration settings enable you to control a wide range of functionality behavior for your zone. There are Device Management settings that let you control how often devices access a ZENworks Server for refreshed information, how often dynamic groups are refreshed, and what levels of messages (informational, warning, or error) are logged by the ZENworks Adaptive Agent. There are Event and Messaging settings, Discovery and Deployment settings, and much more.

Management Zone settings that apply to devices are inherited by all devices in the zone. As discussed in [Section 3.1, “Organizing Devices: Folders and Groups,” on page 19](#), you can override zone settings by configuring them on device folders or on individual devices. This allows you to establish zone settings that apply to the largest number of devices and then, as necessary, override the settings on folders and devices.

By default, your zone settings are preconfigured with values that provide common functionality. You can, however, change the settings to best adapt them to the behavior you need in your environment.

- ♦ [Section 3.5.1, “Modifying Configuration Settings at the Zone,” on page 32](#)
- ♦ [Section 3.5.2, “Modifying Configuration Settings on a Folder,” on page 33](#)
- ♦ [Section 3.5.3, “Modifying Configuration Settings on a Device,” on page 33](#)

3.5.1 Modifying Configuration Settings at the Zone

- 1 In ZENworks Control Center, click the *Configuration* tab.
- 2 In the Management Zone Settings panel, click the settings category (*Device Management*, *Discovery and Deployment*, *Event and Messaging*, and so forth) whose settings you want to modify.

Configuration	Registration	System Information	Asset Inventory	Asset Management	System Updates	
Management Zone Settings						⌵
Device Management						⌵
Category	Description					
Local Device Logging	Enable and configure local logging of warnings and errors encountered by managed devices.					
Device Refresh Schedule	Configure the device refresh interval.					
ZENworks Agent	ZENworks Agent Configuration.					
Registration	Configure registration settings.					
ZENworks Explorer Configuration	Configure the behavior of the ZENworks Explorer on managed devices.					
System Variables	Configure system variables.					
Primary User	Configure the setting for how the primary user is determined.					
Primary Workstation	Configure the setting for how the primary workstation is determined.					
Dynamic Group Refresh Schedule	Configure dynamic group refresh schedule.					
Wake-on-LAN	Configure the Wake-on-LAN settings					
Discovery and Deployment						⌵
Event and Messaging						⌵
Infrastructure Management						⌵
Inventory						⌵
Reporting Services						⌵
Asset Management						⌵

- 3 Click the setting to display its details page.
- 4 Modify the setting as desired.

For information about the setting, see “[Management Zone Configuration Settings](#)” in the *ZENworks 10 Asset Management System Administration Reference* or click the *Help* button in ZENworks Control Center.

- 5 When you have finished modifying the setting, click *OK* (or *Apply*) to save your changes.

If the configuration setting applies to devices, the setting is inherited by all devices in the zone unless the setting is overridden at a folder level or a device level.

3.5.2 Modifying Configuration Settings on a Folder

- 1 In ZENworks Control Center, click the *Devices* tab.
- 2 In the Devices panel (on the *Managed* tab), browse for the folder whose settings you want to modify.
- 3 When you’ve found the folder, click *Details* next to the folder name to display the folder’s details.
- 4 Click the *Settings* tab.
- 5 In the Settings panel, click the settings category (*Device Management*, *Infrastructure Management*, and so forth) whose settings you want to modify.

Devices > Workstations

Workstations

Summary Settings

Settings		
Device Management		
Category	Description	Inherited From
Local Device Logging	Enable and configure local logging of warnings and errors encountered by managed devices.	(System)
Device Refresh Schedule	Configure the device refresh interval.	(System)
ZENworks Agent	ZENworks Agent Configuration.	(System)
Registration	Configure registration settings.	(System)
ZENworks Explorer Configuration	Configure the behavior of the ZENworks Explorer on managed devices.	(System)
System Variables	Configure system variables.	---
Primary User	Configure the setting for how the primary user is determined.	---
Device Dynamic Rename	Enables automatic renaming of devices.	(System)
Infrastructure Management		
Inventory		
Asset Management		

- 6 Click the setting to display its details page.
- 7 Modify the setting as desired.

For information about the setting, see “[Management Zone Configuration Settings](#)” in the *ZENworks 10 Asset Management System Administration Reference* or click the *Help* button in ZENworks Control Center.


- 8 When you have finished modifying the setting, click *OK* (or *Apply*) to save your changes.

The configuration setting is inherited by all devices in the folder, including any devices contained in subfolders, unless the setting is overridden on a subfolder or individual device.

3.5.3 Modifying Configuration Settings on a Device

- 1 In ZENworks Control Center, click the *Devices* tab.

- 2 In the Devices panel (on the *Managed* tab), browse for the device whose settings you want to modify.
- 3 When you've found the device, click the device name to display the its details.
- 4 Click the *Settings* tab.
- 5 In the Settings panel, click the settings category (, *Device Management*, *Infrastructure Management*, and so forth) whose settings you want to modify.



- 6 Click the setting to display its details page.
- 7 Modify the setting as desired.
For information about the setting, see “**Management Zone Configuration Settings**” in the *ZENworks 10 Asset Management System Administration Reference* or click the *Help* button in ZENworks Control Center.
- 8 When you have finished modifying the setting, click *OK* (or *Apply*) to save your changes.

ZENworks Adaptive Agent Deployment

4

Novell® ZENworks® 10 Asset Management provides a variety of methods you can use to deploy the ZENworks Adaptive Agent to the devices you want to manage. This section covers two of the most common methods: a Web installation and a ZENworks Control Center deployment task. For information about the other methods, see the *ZENworks 10 Discovery, Deployment, and Retirement Reference*.

If you plan to use a deployment task to install the Adaptive Agent to devices, you must first either use network discovery or file import to add the target devices to your Management Zone. The first two sections listed below explain how to use network discovery and file import. The remaining section provides installation instructions for the ZENworks Adaptive Agent.

- ♦ [Section 4.1, “Discovering Network Devices,” on page 35](#)
- ♦ [Section 4.2, “Importing Devices,” on page 36](#)
- ♦ [Section 4.3, “Installing the ZENworks Adaptive Agent,” on page 37](#)

NOTE: If a device does not meet the requirements for installing the ZENworks Adaptive Agent (see “[Managed Device Requirements](#)” in the *ZENworks 10 Asset Management Installation Guide*), you might be able to install the Inventory Only Module on it to support inventorying of the device. For more information, see the *ZENworks 10 Discovery, Deployment, and Retirement Reference*.

4.1 Discovering Network Devices

If you want a ZENworks Server to automatically deploy the ZENworks Adaptive Agent to devices, you must first add the devices to your Management Zone. To do this, you have two options: 1) you can use the ZENworks discovery technology to search for devices on your network and display them in ZENworks Control Center or 2) you can import them from a comma-separated values (CSV) file.

This section explains how to use the discovery technology. If you want to know more about importing devices from a CSV file, see [Section 4.2, “Importing Devices,” on page 36](#).

There are two types of discoveries you can perform:

- ♦ **IP discovery:** Lets you specify an IP address range. By default, it uses seven discovery technologies (WMI, WinAPI, MAC Address, ZENworks, SNMP, SSH, and NMAP). Each discovery technology returns varying levels of information (OS version, DNS name, and so forth) about the discovered device.
- ♦ **LDAP discovery:** Lets you specify an LDAP directory context to search for all device-type objects (workstations, servers, and so forth). Device objects that are found are queried for well-known attributes (dnsHostName, OperatingSystem, wmNameDNS, wmNameOS, and so forth) to attempt to determine the OS version and DNS name of the device.

To perform either of the discoveries, you must create a discovery task. The discovery task lets you identify the source (IP address range or LDAP directory) that you want to search, specify the credentials required to retrieve information from discovered devices, schedule the date and time you

want to start the discovery, and select the ZENworks Server you want to perform the discovery. For more information on how to create the discovery tasks, see the *ZENworks 10 Discovery, Deployment, and Retirement Reference*.

4.2 Importing Devices

If you want a ZENworks Server to automatically deploy the ZENworks Adaptive Agent to devices, you must first identify the devices within your Management Zone. To do this, you have two options: 1) you can import them from a comma-separated values (CSV) file, or 2) you can use the ZENworks discovery technology to search for devices on your network and display them in ZENworks Control Center.

This section explains how to import devices from a CSV file. If you want to know more about using discovery technology, see [Section 4.1, “Discovering Network Devices,” on page 35](#).

When you import information from a CSV file, you map the CSV fields to ZENworks database fields. At a minimum, the CSV file must contain the DNS name or IP address for each device you want to import.

To import devices from a CSV file:

- 1 In ZENworks Control Center, click the *Deployment* tab.



- 2 In the *Deployment Activities* list in the left navigation panel, click *Import Deployable Devices* to launch the Import Devices from CSV File Wizard.

[Deployment](#) > **New Discovery Task Wizard**

Import Devices from CSV file

Step 1: Select file to import

Select a comma separated value file that contains information about the devices you want to import

CSV file

- 3 Complete the wizard using information from the following table to fill in the fields.

Wizard Page	Details
Select File to Import page	Browse for and select the CSV file that contains the devices you want to import. At a minimum, the CSV file must contain the DNS name or IP address for each device you want to import.
Configure Import	<p>Map the columns in the CSV file to the device fields in the ZENworks database. At a minimum, you must map the CSV file's DNS name or IP address to the ZENworks database's DNS Name field or IP Address field.</p> <p>To create the information mappings:</p> <ol style="list-style-type: none"> 1. Click <i>Add</i> to display the Specify Import Columns dialog box. 2. Fill in the following fields: <p>Field: Select the device field you want to map to a column in the CSV file.</p> <p>Column: Specify the number of the column to map to the selected field.</p> 3. Click <i>OK</i> to create the information mapping and add it to the list. 4. To verify that the field is mapped to the correct column, click <i>Show Sample</i>. 5. Repeat the above steps to create and verify additional information mappings.

When you finish the wizard, the devices are added to the list in the Deployable Devices panel.


4.3 Installing the ZENworks Adaptive Agent

The following sections provide instructions for using the Web installation or a ZENworks Control Center deployment task to install the ZENworks Adaptive Agent on a device.

- [Section 4.3.1, “Manual Installation,” on page 37](#)
- [Section 4.3.2, “ZENworks Control Center Deployment Task,” on page 38](#)

4.3.1 Manual Installation

- 1 Make sure the device meets the necessary requirements (see “[Managed Device Requirements](#)” in the *ZENworks 10 Asset Management Installation Guide*).
- 2 On the target device, open a Web browser to the following address:
<https://server/zenworks-setup>
where *server* is the DNS name or IP address of a ZENworks Server.



The Web browser displays a list of deployment packages for the Adaptive Agent. For each architecture (32-bit and 64-bit), there are two types of packages:

Network: The network package downloads and installs only the preagent to the target device; the preagent then downloads and installs the ZENworks Adaptive Agent from the ZENworks Server.

Standalone: The standalone package downloads the preagent and Adaptive Agent to the target device; the preagent then installs the Adaptive Agent from the local device. The standalone package is useful when you need to install the ZENworks Adaptive Agent to a device that is currently disconnected from the network. You can save the package to removable media (CD, USB flash drive, and so forth) and have the standalone device run the package from the media. The Adaptive Agent is installed to the device, but no registration or management occurs until the device connects to the network.

- 3 Click the name of the deployment package you want to use; save the package to the device's local drive or run it from the ZENworks Server.

- 4 If you downloaded the package, launch the package on the device.

For information about options you can use with the package when launching it from a command line, see “[Manually Deploying the Agent](#)” in the *ZENworks 10 Discovery, Deployment, and Retirement Reference*.

- 5 Upon completion of the installation, a message is displayed asking whether to reboot. Select one of the following options:

- ♦ Do nothing and auto-reboot occurs after 5 minutes.
- ♦ Click *Cancel*. You will need to reboot later.
- ♦ Click *OK* to reboot immediately.

When the device reboots, it is registered in the Management Zone and the ZENworks icon is placed in the notification area (system tray).

In ZENworks Control Center, the device appears under the \Servers folder structure or \Workstations folder structure on the Devices page.

4.3.2 ZENworks Control Center Deployment Task

To install the Adaptive Agent by using a deployment task, the target device must be displayed in ZENworks Control Center. This means you must have already completed [Section 4.1, “Discovering Network Devices,”](#) on page 35 or [Section 4.2, “Importing Devices,”](#) on page 36.

To create a deployment task:

- 1 In ZENworks Control Center, click the *Deployment* tab.

The Deployable Device panel lists all the devices (imported or discovered) to which you can deploy the Adaptive Agent.

Deployable Devices						Advanced
Delete Action View						
<input type="checkbox"/>	Name	IP Address	Operating System	Discovered Date	Deployment Status	
<input type="checkbox"/>	roshambo-t60p.dnsdhcp.provo.novell.com	137.65.164.51	Unknown OS	Jun 25, 2007	Inactive	
<input type="checkbox"/>	dvandenbosdp360.dnsdhcp.provo.novell.com	137.65.164.52	Unknown OS	Jun 25, 2007	Inactive	
<input type="checkbox"/>	rbf-dell.dnsdhcp.provo.novell.com	137.65.164.53	Unknown OS	Jun 25, 2007	Inactive	
<input type="checkbox"/>	kevinsxp-pro.dnsdhcp.provo.novell.com	137.65.164.54	Unknown OS	Jun 25, 2007	Inactive	
1 - 4 of 4						show 25 items

2 In the Deployment Tasks panel, click *New* to launch the Deploy Device Wizard.

Deployment > Deploy Device Wizard

Deploy Device Wizard

Step 1: Enter Deployment Task Name


Name: *

Description:

* Fields marked with an asterisk are required.


<< Back Next >> Cancel

3 Complete the wizard using information from the following table to fill in the fields.

Wizard Page	Details
Enter Deployment Task page	Specify a name for the task. The name cannot include any of the following characters: / \ * ? : " ' < > ` % ~
Select Devices page	<ol style="list-style-type: none"> Click <i>Add</i> to display the Discovered Device Browser dialog box. The default view displays all discovered devices in your Management Zone. Click  to select a device. When you have finished selecting devices, click <i>OK</i> to return the Select Devices page. The devices you selected are displayed in the list.
Enter Credentials page > <i>Save Credentials to DataStore</i> field	<p>The Enter Credentials page lets you provide the usernames and passwords required to deploy the Adaptive Agent to the devices included in the task.</p> <p>Unless you save the credentials, they are stored only in memory. Saved credentials are encrypted in the database for increased security.</p> <p>Credentials that are not saved are cleared from memory when the ZENworks Server is restarted. If you are creating a scheduled deployment task, you might want to save the credentials to ensure that they are still available when the deployment is performed.</p>

Wizard Page	Details
Enter Credentials page > <i>Credentials</i> field	<p>To add a credential:</p> <ol style="list-style-type: none"> Click <i>Add</i> to display the Enter Credential Information dialog box. In the <i>Username</i> field, specify the appropriate username. <p>To deploy the Adaptive Agent, the ZENworks Server must be able to map a drive to the device's administrative share (ADMIN\$). This requires the following credentials:</p> <ul style="list-style-type: none"> ♦ If the device is a member of a domain: You can use a domain or local Administrator group credential. If you use the local credential, you must specify the username as <code>workstation_name\username</code> to distinguish it from domain credentials. ♦ If the device is not a member of a domain: You must use a local Administrator group credential. <ol style="list-style-type: none"> Enter the user password in the <i>Password</i> and <i>Reenter Password</i> fields. Click <i>OK</i> to save the credential. <p>Depending on your environment, one credential might not provide access to all of the devices where you want to deploy the Adaptive Agent. In this case, you need to add as many credentials as necessary to cover the devices included in the task. The ZENworks Server uses the first credential that works.</p>
Select Schedule page	<p>The Select Schedule page lets you choose whether you want the task to run as soon as it is created (the <i>Now</i> option) or if you want to schedule the task to run at a future date and time. If you select <i>Scheduled</i>, choose one of the following schedules:</p> <p>No Schedule: Indicates that no schedule has been set. The task does not run until a schedule is set or it is manually launched. This is useful if you want to create the task and come back to it later to establish the schedule or run it manually.</p> <p>Date Specific: Specifies one or more dates on which to run the task.</p> <p>Recurring: Identifies specific days each week, month, or a fixed interval on which to run the task.</p> <p>For more information about the schedules, click the <i>Help</i> button.</p>
Select Primary Server page > <i>Primary Server</i> field	<p>Select the ZENworks Server that you want to perform the deployment task.</p>

Wizard Page	Details
Select Windows Proxy page > Use Windows Proxy For Windows Primary Server field	<p>Select this option if you want to use a Windows Proxy instead of the Windows Primary Server to perform the deployment task.</p> <p>A Windows Proxy can be used for:</p> <ul style="list-style-type: none"> ♦ Linux Primary Servers that cannot perform Windows-specific discovery and deployment tasks ♦ Linux Primary Servers that cannot perform Windows-specific discovery and deployment tasks <p>Windows Servers if the devices to be discovered or deployed are in a different subnet than the Primary Server.</p> <hr/> <p>NOTE: This option is displayed only if a Windows Primary Server is selected on the Select Primary Server page.</p> <hr/> <p>For deployment, you need to add File and Printer Sharing as an exception in the Windows Firewall configuration settings. By default, the scope of the exception applies only to a local subnet. If the target device is in a different subnet than the Primary Server from which the deployment is run, you also need to add the IP address of the Primary Server as an exception. However, if you use a Windows Proxy in the same subnet as a target device, you do not need to change the scope of the Windows Firewall exception.</p>
Select Windows Proxy page > <i>Override Zone Windows Proxy Settings</i> field	<p>Chose to override the Windows Proxy settings configured at the Management Zone.</p> <p>If you want to configure the settings on a task, you must select <i>Override Zone Windows Proxy Settings</i> before you can modify the settings.</p> <p>The Windows Proxy Settings panel lets you specify a managed Windows device in your zone to perform discovery and deployment tasks in place of a ZENworks Server. This is designed primarily to enable ZENworks Servers running on Linux to offload discovery tasks that use Windows-specific discovery technologies such as WMI and WinAPI and deployment tasks that involve Windows managed devices.</p> <p>In order to protect information, such as a discovery credential, that is passed between the ZENworks Server and the Windows Proxy, the connection is secured through SSL.</p> <p>Windows Proxy: Select the managed Windows device (server or workstation) that you want to perform discovery and deployment tasks in behalf of Linux-based ZENworks Servers.</p> <p>Windows Proxy Timeout: Specify the number of seconds you want the ZENworks Server to wait for a response from the Windows Proxy. Any responses received after the specified timeout period are discarded.</p>

Wizard Page	Details
General Options page > <i>Deployment Package</i> field	<p>Depending upon the processor architecture of the managed device, select the deployment package to be used for installing ZENworks Adaptive Agent on the device.</p> <p>If you are not sure about the device's processor architecture, choose the package with target architecture as All, which applies to 32-bit and 64-bit platforms. If the selected package has been deleted from the Primary Server, then the default deployment package is deployed.</p>
General Options page > <i>Specify Agent Installation Folder</i> field	<p>Specify the directory on the managed device where you want to install ZENworks Adaptive Agent. By default, the agent is installed to the directory specified in the %ZENWORKS_HOME% system environmental variable or to the %ProgramFiles%\novell\zenworks directory if the variable is not set on the managed device.</p> <p>Ensure that the installation path does not contain spaces.</p> <hr/> <p>NOTE: If the directory you specify cannot be created, then the agent is installed in the default location.</p> <hr/>
General Options page > <i>Reboot Option</i>	<p>After installation of the ZENworks Adaptive Agent, a device must reboot to make the Adaptive Agent functional. Do the following:</p> <ol style="list-style-type: none"> Select the desired reboot option. <ul style="list-style-type: none"> ♦ Immediate: To reboot immediately after installation of the Adaptive Agent, select <i>Immediate</i> to force the device ♦ Manual: To allow the user to manually reboot the device at his or her convenience, select <i>Manual</i>. ♦ Scheduled: To reboot the device at a specified time, select <i>Scheduled</i>. Fill in the schedule's fields. <ul style="list-style-type: none"> ♦ Start Date: Click  to display a calendar you can use to select a date for the event. ♦ Start Time: Specify the time at which the event must start. ♦ Use Coordinated Universal Time (UTC): The Start Time is converted to Universal Coordinated Time (UTC). Select this option to indicate that the Start Time you entered is already in Coordinated Universal Time and should not be converted. For example, suppose you are in the Eastern time zone. If you enter 10:00 a.m. and select this option, the Start Time is scheduled for 10:00 UTC. If you don't select this option, the Start Time is scheduled for 14:00 UTC because Eastern time is UTC - 4 hours. (Optional) Select the <i>Do Not Prompt for Reboot</i> option if you do not want the reboot prompt message to be displayed.

Wizard Page	Details
Add Registration Key page	<p>(Optional) Select a registration key to use during the registration portion of the deployment process. A registration key provides information about the folders and groups to which a device is assigned during registration. Selecting a registration key is optional; if you don't select one, registration rules are used to determine the folder and group assignments. To deploy to servers or workstations, choose a server registration key or a workstation registration key respectively.</p> <p>For more information about registration keys and rules, see Section 3.2, "Registering Devices," on page 23.</p>
Pre/Post Deployment page	<p>(Optional) Specify commands that you want run before and after the Adaptive Agent is installed on a device. For example, you can execute operating system commands, run scripts, and launch executables.</p> <p>The commands are passed to the preagent as part of the deployment task package. The preagent executes the commands in the system space, so you must specify commands that do not require user interaction.</p> <p>For more information about pre-deployment and post-deployment commands, click the <i>Help</i> button.</p>

You can also use the `deployment-task-create` command in the `zman` utility to create a deployment task. For more information, see "[Deployment Commands](#)" in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

Asset Management

5

After you've configured your Management Zone and deployed the ZENworks® Adaptive Agent (or Inventory-Only Module) to devices, you're ready to start managing the software and hardware assets on those devices.

The following sections provide explanations and instructions for collecting software and hardware inventory from devices, monitoring software usage on devices, and monitoring software license compliance.

- ♦ [Section 5.1, “Collecting Software and Hardware Inventory,” on page 45](#)
- ♦ [Section 5.2, “Monitoring Software Usage,” on page 48](#)
- ♦ [Section 5.3, “Monitoring License Compliance,” on page 49](#)

5.1 Collecting Software and Hardware Inventory

When you inventory of a device, ZENworks Asset Management collects both software and hardware information from the device. Using ZENworks Control Center, you can view the inventory for an individual device, or you can generate reports for multiple devices based on specific criteria.

You can use the software inventory for a variety of purposes, including tracking usage of specific applications and ensuring that you have sufficient licenses for all copies of the application being used. For example, assume that your company owns 50 licenses of a word processing software. You do a software inventory and find that it is installed on 60 devices, which means that you are out of compliance with your license agreement. However, after viewing the usage reports for the software for the past 6 months, you see that it is actually being used on only 45 devices. To become compliant with the license agreement, you uninstall the software from the 15 devices that are not using it.

You can use the hardware inventory for a variety of purposes as well, including ensuring that your hardware meets the requirements for running specific software. For example, assume that your Accounting department wants to roll out a new version of their accounting software. The new software has increased processor, memory, and disk space requirements. Using the hardware inventory collected from your devices, you can create two reports, one that lists all devices that meet the requirements and one that lists the devices that don't meet the requirements. Based on the reports, you distribute the software to the compliant devices and create an upgrade plan for the noncompliant devices.

By default, devices are automatically scanned at 1:00 a.m. the first day of each month. You can modify the schedule, as well as many other *Inventory* configuration settings, on the *Configuration* tab in ZENworks Control Center.


The following sections provide instructions for initiating a device scan and using the collected inventory:

- ♦ [Section 5.1.1, “Initiating a Device Scan,” on page 46](#)
- ♦ [Section 5.1.2, “Viewing a Device Inventory,” on page 46](#)
- ♦ [Section 5.1.3, “Generating an Inventory Report,” on page 47](#)
- ♦ [Section 5.1.4, “Where to Find More Information,” on page 48](#)

5.1.1 Initiating a Device Scan

You can initiate a scan of a device at any time.

- 1 In ZENworks Control Center, click the *Devices* tab.
- 2 Navigate the *Servers* or *Workstations* folder until you locate the device you want to scan.
- 3 Click the device to display its details.



- 4 In the task list located in the left navigation pane, click *Server Inventory Scan* or *Workstation Inventory Scan* to initiate the scan.

The QuickTask Status dialog box displays the status of the task. When the task is complete, you can click the *Inventory* tab to view the results of the scan.

You can also use the `inventory-scan-now` command in the `zman` utility to scan a device. For more information, see “[Inventory Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

5.1.2 Viewing a Device Inventory

- 1 In ZENworks Control Center, click the *Devices* tab.
- 2 Navigate the *Servers* or *Workstations* folder until you locate the device you want to scan.
- 3 Click the device to display its details.

4 Click the *Inventory* tab.

Devices > Servers > blr-s

blr-s

Summary Inventory Relationships Settings Statistics

Summary

Last Scan Date: 1:00 AM

Host Name: BLR-S

Dept: SRM

Location:

Site	Building	Floor	Room
Good	D block	89	37856

[Detailed Hardware/Software Inventory](#)

Hardware:

Asset Tag:	No Asset Tag
Serial Number:	
System:	Xeon 2400 System
Operating System:	Microsoft Windows Server 2003 Enterprise Edition 5.2 1 3790
Mac Address:	000C29E89227
Total Memory:	2 GB
Free Hard Disk Space:	1.08 GB
Total Hard Disk Space:	16.11 GB

5.1.3 Generating an Inventory Report

ZENworks Asset Management includes several standard reports. In addition, you can create custom reports to provide different views of the inventory information.

1 In ZENworks Control Center, click the *Reports* tab.

Novell ZENworks Logout Administrator

DATA_VAL_78774 Help

Home Devices Users Deployment Reports Configuration Asset Management

Frequently Used

- New
- bundle-group
- copy-files
- test
- blr-srm-r7c
- 4
- 1
- Windows 2000 Workstatio
- 2
- role3

BusinessObjects Enterprise Reporting

[BusinessObjects Enterprise InfoView](#)

Inventory Standard Reports

Group

- Device Lists
- Software Applications
- Software Files
- Hardware Components
- Upgrade Readiness

Inventory Custom Reports

New	Edit	Delete	Action
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Name	Report Count		
<input type="checkbox"/> Hardware Components	4		
<input type="checkbox"/> Local Product Creation	2		
<input type="checkbox"/> Software Applications	7		
<input type="checkbox"/> Systems	7		

1 - 4 of 4 show 10 items

2 In the Inventory Standard Reports panel, click *Software Applications*.

Reports	
Name	Description
Antivirus Details	Antivirus definition files with links to devices where installed
Software Applications By Category	Count of installed software products by category and subcategory
Software Applications By Manufacturer	Count of installed software products by manufacturer
Software Applications By OS and Product	Count of installed software products by product name
Duplicate Serial Numbers	Lists software products installed with multiple instances of the same serial number
High Bandwidth Applications	Count of popular multimedia and file-sharing apps such as KaZaa and Gnutella
Hot Fix Details	Hot fixes and security patches with links to list of devices where installed
Microsoft Products	Count of installed Microsoft products grouped by Microsoft-specific classifications
Operating Systems	Count of devices by installed operating system
OS Service Packs	Count of devices by installed operating system and service pack

- 3 Click the *Operating System* report to generate the report.

Using the options at the bottom of the report, you can save the generated report as a Microsoft Excel* spreadsheet, CSV (comma-separated values) file, PDF file, or PDF Graph file.

5.1.4 Where to Find More Information


For more information about inventory, see the *ZENworks 10 Asset Inventory Reference*.

5.2 Monitoring Software Usage

After you've inventoried devices, you can run reports to view how much the devices' applications are used. ZENworks Asset Management includes standard reports for application usage by product, user, and device. You can also customize reports to provide more detailed or focused information. For example, Asset Management includes a predefined custom report that shows application that have not been used in the last 90 days.

To run a report that shows how much a specific application is used:

- 1 In ZENworks Control Center, click the *Asset Management* tab, then click the *Software Usage* tab.



- 2 In the Software Usage Standard Reports panel, click *Application Usage* to display the list of application usage reports.

Reports		Grouping Criteria
Name	Description	<input checked="" type="radio"/> Zone <input type="radio"/> Folder <input type="radio"/> Group <input type="radio"/> Demographic
Total Application Usage by Product	Sum of local and served application usage organized by product	
Total Application Usage by User	Sum of local and served application usage organized by user	
Total Application Usage by Device	Sum of local and served application usage organized by device	
Local Application Usage by Product	Local application usage organized by product	
Local Application Usage by User	Local application usage organized by user	
Local Application Usage by Device	Local application usage organized by device	
Served Application Usage by Product	Served application usage organized by product	
Served Application Usage by Server	Served application usage organized by server	
Served Application Usage by User	Served application usage organized by user	
Served Application Usage by Device	Served application usage organized by device	
Usage Collection history	History of usage data collection	

3 In the Reports panel, click *Local Application Usage by Product*.

Local Application Usage by Product		Run Date: 3/16/09
Products from 10 Software Manufacturer(s) Installed on 2 Device(s)		
Manufacturer	Installations	
Cinematronics	1	
Macromedia	1	
Microsoft	45	
Novell	13	
Sun	6	
Sun Microsystems	32	
Sybase	1	
Symantec	1	
VMware	2	
Yahoo!	1	

[Excel](#) [CSV](#) [PDF](#) [Graph](#)

The report shows all the products, grouped by software manufacturer, that are installed on the devices.

4 Find a manufacturer whose products you want to see, then click the number in the Installations column to display the installed products.

The resulting report shows the current number of installations for each product, how many of the installations have been used, when it was last used, and other usage information.

5 If you want to change the time period for the report, or change the list of products displayed (all products, used products, or unused products), click *Change Time Period/Filters* at the bottom of the report.


There are many other standard and predefined custom reports that you can use. For additional information about application usage reports, see the *ZENworks 10 Asset Inventory Reference*.

5.3 Monitoring License Compliance

ZENworks Asset Management enables you to ensure compliance with software license agreements by comparing information about software products you've purchased with installed software products discovered during inventory scans.

Before you begin implementing compliance monitoring, you need to understand the components involved and how they work together, as explained in the following illustration and subsequent text.

Figure 5-1 License Compliance Components



- ♦ You scan the devices in your Management Zone to create a list of software products installed on the devices. These are called *discovered products*. In the above illustration, the inventory scan discovered that ProductA is installed on 15 devices.
- ♦ You create *catalog products* to represent the software products your organization has purchased. Typically, each catalog product corresponds to a specific manufacturer part number. In the above illustration, ProductA is the only catalog product. However, you might have catalog products for ProductA, ProductA Upgrade, and ProductB. Catalog products are added by importing a purchase record or by manually creating the catalog product.
- ♦ You create (or import) *purchase records* to represent the purchase orders or invoices for software products. Each line item in the purchase record lists a catalog product along with the purchase quantity. If a catalog product is listed in multiple purchase records, the catalog product's total licenses equal the purchase quantity for both purchase records. In the above illustration, one purchase record includes 10 licenses of ProductA and another purchase record includes 8 licenses. The total license count for ProductA is 18.
- ♦ You create *licensed products* and associate the corresponding discovered products and catalog products to them. This gives you a single licensed product that includes the number of licenses and installations for the product. The result is a quick view of whether or not the product usage complies with the license agreement. In the above illustration, ProductA has 18 licenses and is installed on 15 devices, so ProductA complies with your license agreement.

The following sections provide instructions for implementing license compliance monitoring. The instructions assume that you've already scanned devices to discover installed software products. If you have not, see [Section 5.1, "Collecting Software and Hardware Inventory," on page 45](#).

- ♦ [Section 5.3.1, "Recording Software Purchases," on page 51](#)
- ♦ [Section 5.3.2, "Creating Licensed Products," on page 53](#)
- ♦ [Section 5.3.3, "Viewing Compliance Data," on page 55](#)

5.3.1 Recording Software Purchases

To record software purchases, you need to make sure the purchased products exist as catalog products and then create the purchase record. The easiest way to do this is to use an import file that includes your purchase orders. When you use an import file, the purchase record is created and any products that are not already listed in the product catalog are added to it. Importing purchase records requires your software reseller to provide you with an import file in one of the formats that ZENworks Asset Management supports. If you are unable to use an import file, you can manually create the catalog products and purchase records you need.

- ♦ “Importing Purchase Records” on page 51
- ♦ “Manually Creating Catalog Products and Purchase Records” on page 52

Importing Purchase Records

ZENworks Asset Management supports the import file formats of several software resellers:

- ♦ CompuCom Software Compliance Report
- ♦ Insight ZENworks Asset Management Reseller Connector Report
- ♦ KMD Asset Report
- ♦ SHI License Compliance Report
- ♦ Softchoice Product History Report

If you don’t have an import file from a software reseller and you want to create your own import file, you can use the standard ZENworks Asset Management import file format. For information, see “ZENworks Asset Management Import File Formats” in the *ZENworks 10 Asset Management Reference*.

To import purchase records from one of the supported file formats:

- 1 In ZENworks Control Center, click the *Asset Management* tab, then click the *License Management* tab.
- 2 In the License Management panel, click *Purchase Records*.

[License Management](#) > Purchase Records

Purchase Records			Import Status
New ▾ Move... Delete Action ▾			
<input type="checkbox"/>	PO #	Order Date	Reseller
No items available.			


- 3 Click *Action* > *Start Import*.
- 4 In the Import dialog box, click *Browse* to locate and select the import file.
- 5 Click *OK* to start the import.

During the import, the progress is displayed above the Purchase Records list. You can also click the Import Status tab to see the progress of the import. When the import is complete, the new purchase records are added to the list.

As part of the import process, ZENworks Asset Management creates catalog products for any purchase record products not already included in the product catalog.

- 6 Continue with [Section 5.3.2, “Creating Licensed Products,”](#) on page 53.

Manually Creating Catalog Products and Purchase Records

- 1** In ZENworks Control Center, click the *Asset Management* tab, then click the *License Management* tab.
- 2** Create catalog products for any products that you want to include in purchase records. To do so:
 - 2a** In the License Management panel, click *Catalog Products*.
 - 2b** Click *New > Catalog Product* to launch the Create New Catalog Product Wizard.
 - 2c** Fill in the following fields:
 - Manufacturer:** Select the software manufacturer from the list. If the correct manufacture is not listed, type the manufacturer name (for example, Novell, Symantec, or Microsoft).
 - Product:** Type the name of the product. It must be unique in the product catalog.
 - Product Type - Notes:** These fields are optional. You can use them to further identify the product.
 - Exclude:** Do not select this check box.
 - 2d** Click *Next* to display the Summary page, then click *Finish* to add the product to the catalog.
 - 2e** Repeat **Step 2b** through **Step 2d** to create additional catalog products.
 - 2f** When finished, click *License Management* (in the breadcrumb path at the top of the page) to return to the License Management page.
- 3** Create your purchase records. To do so:
 - 3a** In the License Management panel, click *Purchase Records*.
 - 3b** Click *New > Purchase Record* to launch the Create New Purchase Record Wizard.
 - 3c** Fill in the following fields:
 - PO Number:** Specify the purchase order number or invoice number associated with the software product purchase.
 - Order Date:** Select the date the software was purchased.
 - Recipient - Reseller:** These fields are optional. You can use them to further identify the purchase record.
 - 3d** Click *Next* to display the Summary page.
 - 3e** Select the *Define Additional Properties* box, then click *Finish* to create the purchase record and display its Purchase Details page.
 - 3f** Click *Add* to display the Add Purchase Detail dialog box, then fill in the following fields:
 - Product:** Click  to browse for and select the catalog product that represents a software product you want included on the purchase record.
 - Quantity:** Specify the quantity of product purchased. For example, if the catalog product you selected is ProductA 10-Pack and the purchase order was for 5 ProductA 10-Packs, specify 5.
 - Unit MSRP - Extended Price:** These fields are required. Specify the Manufacturer Suggested Retail Price (MSRP), the price you paid per unit, and the extended price.
 - Invoice # - Comments:** These fields are optional. You can use them to further identify the purchase.

- 3g** Click *OK*.
- 3h** Repeat **Step 3f** through **Step 3g** to add additional products to the purchase record.
- 4** Continue with the next section, **Creating Licensed Products**.


5.3.2 Creating Licensed Products

After you've recorded your software purchases by creating purchase records and catalog products (if necessary), you need to create licensed products and associated the appropriate discovered products and catalog products with them. The licensed product then reflects the total number of licenses and installations for the product.


To create licensed products and associate them with discovered products and catalog products:

- 1** In ZENworks Control Center, click the *Asset Management* tab, then click the *License Management* tab.
- 2** In the License Management panel, click *Licensed Products*.

[License Management](#) > **Licensed Products**

Compliance Refresh Start: March 18, 2009 10:51:56 AM				Finish: March 18, 2009 10:51:58 AM	
Started By: Administrator				0 Licensed Products	
Licensed Products					
 New ▾ Move... Delete Action ▾					
<input type="checkbox"/>	Name ▲	Status	Discovered Products	Catalog Products	License Quantity
			Allocated Quantity		
No items available.					

- 3** In the Licensed Products panel, click *Action > Auto-Reconcile: Create Licensed Products* to launch the Auto-reconcile Wizard. Complete the wizard using information from the following table to fill in the fields.

Wizard Page	Details
Discovered Product Filter page	<p>Select the discovered products to reconcile. Reconciling a discovered product causes a licensed product to be created for it.</p> <p>Select <i>Any</i> to reconcile all discovered products; select <i>Products Specified Below</i> and provide a manufacturer and product name to reconcile a specific product.</p>
Select Licensed Products to Create page	<p>This page lists the licensed products that will be created for the discovered products. You can select or deselect the licensed products to create; a licensed product is only created if its check box is selected.</p> <p>In addition, if the wizard can match any catalog products to a discovered product, the catalog products are listed as well. If you select a catalog product, its licenses are associated with the licensed product.</p> <p>If the wizard is unable to match any catalog products to a discovered product, you can manually assign catalog products after completing the wizard.</p>
Destination Folder page	<p>Select the folder where you want to place the new licensed products.</p> <p>The field defaults to the current folder (the folder from which you launched the Auto-Reconcile wizard). To specify another folder, click  to browse for and select the folder. The folder must already exist; you cannot use the selection dialog to create a new folder.</p>
License Entitlements page	<p>Add a description for the license entitlement. The description typically reflects the software purchase (for example, Initial Purchase: 100 Pack or Version 5 to 6: 100 Upgrade).</p> <p>Select one of the following license models:</p> <ul style="list-style-type: none"> ♦ Per-Installation: Software is licensed per-installation. ♦ OEM: Software is licensed as part of the OEM package. ♦ Machine: Software is licensed per machine.
Auto-reconcile Create Summary page	<p>Review your data and press finish to create the licensed product and reconcile it with the associated discovered product and catalog product(s).</p>

- Continue with the next section, **Viewing Compliance Data**, for information about monitoring compliance.

5.3.3 Viewing Compliance Data

There are two views you can use to monitor the compliance status of your licensed products. You can view the Licensed Products page to get a compliance status summary for all products, or you can generate the Software Compliance report to see more detailed information.

- ♦ “Viewing the Compliance Status Summary” on page 55
- ♦ “Generating the Software Compliance Report” on page 55

Viewing the Compliance Status Summary

- 1 In ZENworks Control Center, click the *Asset Management* tab, then click the *License Management* tab.
- 2 In the License Management panel, click *Licensed Products* to display the Licensed Products page.

[License Management](#) > [Licensed Products](#)

Compliance Refresh Start: March 18, 2009 1:10:51 PM
Started By: (automatic single refresh)

Finish: March 18, 2009 1:10:52 PM
1 Licensed Product

Licensed Products						
New Move... Delete Action						
Name	Status	Discovered Products	Catalog Products	License Quantity	Allocated Quantity	
Microsoft Office Professional 2003 2003				5	0	
Microsoft Windows Server 2003 5.2				1	0	
Microsoft Windows XP Professional 5.1				1	0	

1 - 3 of 3 show 25 items

The Licensed Products list displays all licensed products and their current compliance status:

- ♦ The software product is properly licensed. The number of purchased licenses equals the number of installations.
- ♦ The software product is over licensed. There are more purchased licenses than installations.
- ♦ The software product is under licensed. There are fewer purchased licenses than installations.

Generating the Software Compliance Report

- 1 In ZENworks Control Center, click the *Asset Management* tab, then click the *License Management* tab.
- 2 In the License Management panel, click *License Management Reports*.

License Management Standard Reports	
Group	
	Software Compliance
	Unreconciled Products
	Purchases
	Suites
	Other Reports

License Management Custom Reports	
New Edit Delete Action	
Name	Report Count
Software Compliance	4

1 - 1 of 1 show 10 items

- 3 In the License Management Standard Reports panel, click *Software Compliance*.
- 4 In the Reports panel, click *Compliance Report*.

Software Compliance Report

Run Date: 8/1/07

Report Time Period: Previous 3 Months

Unreconciled Catalog Products: 233

View: All

Unreconciled Discovered Products: 26

Compliance Calculated As of: 7/31/07 11:00:05 PM

1 License Records

Manufacturer	Product	Version	Status	Consumption Data Source	License Quantity	Installed Quantity	Consumed Licenses	Over Licensed Quantity	Under Licensed Quantity	Active Usage Quantity	Unused Installations	More Recent Recalc.
Firefox				Inventory	0	2	2	0	2	0	2	Yes

Filter by:

☐ Manufacturer

☐ Value

Group by:

☐ None

Search

A report appears showing compliance data by license. You can filter the data by compliance status, manufacturer and value, or demographic criteria. Drill in to *License Quantity* to see compliance details for a particular licensed product. For information on other reports, see the *ZENworks 10 Asset Inventory Reference*.

Device Retirement

6

If you retire a device, the device is removed from your ZENworks Management Zone. Retiring a device is different from deleting a device. When you retire a device, its GUID is retained (as opposed to when you delete a device, which also deletes its GUID). As a result, all inventory information is retained and is assessable but all assignments (folder, configuration settings, and so forth) are removed. If you unretire the device in the future, its assignments are restored. You can retire both managed and inventoried devices.

- ♦ [Section 6.1, “Retiring a Managed Device,” on page 57](#)
- ♦ [Section 6.2, “Retiring an Inventoried-Only Device,” on page 57](#)

6.1 Retiring a Managed Device

To retire or unretire a managed device:

- 1 In ZENworks Control Center, click the *Devices* tab.
- 2 Click the underlined link next to the *Servers* or *Workstations* folder to display the list of servers or workstations in your ZENworks system.

Status	Name	Type	Operating System	Last Contact	Retired
<input type="checkbox"/>	Windows 2000 Servers	Dynamic Server Group			
<input type="checkbox"/>	Windows Server 2003	Dynamic Server Group			
<input type="checkbox"/>	Windows Server 2008	Dynamic Server Group			
<input checked="" type="checkbox"/>	zendoc1b	Server	win2003-se-sp2-x86	3:41 AM	


- 3 Select the check box in front of the server or workstation (you can select multiple devices).

Before you can retire a ZENworks Primary Server, you must first demote it. For more information, see [“Changing the Parent-Child Relationships of Primary Servers”](#) in the *ZENworks 10 Asset Management System Administration Reference*.

- 4 Click *Action* > Retire Device.

or





Click *Action* > Unretire.

The  icon displays in the *Status* column in the *Servers* or *Workstations* list for retired devices. You can mouse over the time to see the full date and time.

6.2 Retiring an Inventoried-Only Device

To retire or unretire an inventoried-only device:

- 1 In ZENworks Control Center, click *Devices* > *Inventoried*.
- 2 Click the underlined link next to the *Servers* or *Workstations* folder to display the list of servers or workstations in your ZENworks system.


Devices						
New Edit Delete Action Quick Tasks						
<input type="checkbox"/>	Status	Name	Type	Operating System	Last Contact	Retired
<input type="checkbox"/>		 Windows 2000 Servers	Dynamic Server Group			
<input type="checkbox"/>		 Windows Server 2003	Dynamic Server Group			
<input type="checkbox"/>		 Windows Server 2008	Dynamic Server Group			
<input checked="" type="checkbox"/>		zendoctb	Server	win2003-se-sp2-x86	3:41 AM	

3 Select the check box in front of the server or workstation you want to retire or unretire (you can select multiple devices).

4 Click *Action > Retire Device*.

or

Click *Action > Unretire Device*.

The  icon displays in the *Status* column in the *Servers* or *Workstations* list for retired devices. You can mouse over the time to see the full date and time.

System Messages and Reports

7

Novell® ZENworks® 10 Asset Management lets you monitor the activity within your Management Zone through system messages and reports.

- ♦ [Section 7.1, “Viewing System Messages,” on page 59](#)
- ♦ [Section 7.2, “Creating a Watch List,” on page 61](#)
- ♦ [Section 7.3, “Generating Reports,” on page 62](#)

7.1 Viewing System Messages

The ZENworks system generates normal (informational), warning, and error messages to help you monitor activities such as the distribution of software and application of policies.

Each ZENworks Server and ZENworks Adaptive Agent creates a log of the activities associated with it. These messages are displayed in ZENworks Control Center in a variety of areas:

- ♦ **System Message Log:** The system message log, located on the System Information page (*Configuration* tab), displays messages from all ZENworks Servers and Adaptive Agents within the zone.
- ♦ **Device Message Log:** A device message log, located on the Summary page for a server or workstation, displays messages generated by the ZENworks Server or the Adaptive Agent. For example, the message log for Workstation1 includes all messages generated by the Adaptive Agent on Workstation1.

7.1.1 Viewing a Summary of Messages

You can view a summary that shows the number of messages generated for the in your zone.


- 1 In ZENworks Control Center, click the *Home* tab.





The screenshot displays the Novell ZENworks Control Center interface. The top navigation bar includes the Novell ZENworks logo, a 'Logout Administrator' link, and a 'Help' dropdown menu. The left sidebar contains a 'Home' tab and various navigation options like 'Devices', 'Users', 'Deployment', 'Reports', 'Configuration', and 'Asset Management'. The main content area is titled 'Message Summary' and features a table with columns for 'Servers', 'Workstations', and 'Total'. The table shows 0 messages for Servers and 1 message for Workstations, totaling 1 message. Below this, there is a 'Device Hot List' section showing a single entry for 'zendoc2a' with 0 messages. The 'Asset Management' section is also visible, showing a table with columns for 'Catalog Products', 'Discovered Products', 'Licensed Products', 'Contracts', and 'Documents'. The 'Watch List' section on the right shows a single entry for 'zendoc2a' with 0 messages.

Message Summary	Servers	Workstations	Total
	0	1	1

Device Hot List	Type	Item
0	0	25 zendoc2a

Asset Management	Catalog Products	Discovered Products	Licensed Products	Contracts	Documents
	258	0	4	262	
	2	0	3	12	
	1	1	1	3	
	0	0	0	0	
	0	-	0	0	


The Message Summary panel displays the status of all in your Management Zone. For example, if two servers have unacknowledged critical messages (messages that you or another administrator have not yet acknowledged as having seen), the  column displays the number 2. You can do the following with the summary:

- Click an object type to display its root folder. For example, click *Servers* to display the Servers root folder (/Servers).
- For any object type, click the number in one of its status columns (, , ) to display a listing of all the objects that currently have that status. For example, to see the list of servers that have a normal status, click the number in the  column.
- For any object type, click the number in the *Total* column to display all of the objects that have critical, warning, or normal messages. For example, click the *Total* count for *Servers* to display a list of all servers that have any type of messages.

7.1.2 Acknowledging Messages

A message remains in a message log until you acknowledge it. You can acknowledge individual messages or acknowledge all messages in the message log at one time.

- In ZENworks Control Center, click the *Devices* tab.
- Navigate the *Servers* folder until you locate a ZENworks Server.
- Click the server to display its details.



- On the *Summary* tab, locate the Message Log panel.

The Message Log panel lists all messages (informational, warning, and error) generated by the ZENworks Server. The following table explains the various ways you can acknowledge and delete messages.

Task	Steps	Additional Details
Acknowledge a message	<ol style="list-style-type: none"> 1. Click the message to display the Message Detail Information dialog box. 2. Click <i>Acknowledge</i>. 	<p>If you decide that you don't want to acknowledge the message, click <i>Finished</i> to dismiss the dialog box. This causes the message to remain in the <i>Message Log</i> list.</p>
Acknowledge all messages	<ol style="list-style-type: none"> 1. In the <i>Tasks</i> list located in the left navigation pane, click <i>Acknowledge All Messages</i>. 	
View all acknowledged or unacknowledged messages	<ol style="list-style-type: none"> 1. Click the <i>Advanced</i> button to display the Edit Message Log page. 	<p>In addition to viewing all acknowledged and unacknowledged messages, you can also view only those messages with a specific status or date, view more details about messages, and acknowledge messages.</p> <p>Click the <i>Help</i> button on the Edit Message Log page for specific information about performing tasks on that page.</p>
Delete a message	<ol style="list-style-type: none"> 1. Click the message to display the Message Detail Log dialog box. 2. Click <i>Delete</i>. 	<p>Deleting a message completely removes the message from your ZENworks system.</p>





You can also use the `messages-acknowledge` command in the `zman` utility to acknowledge messages associated with devices. For more information, see “[Message Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

7.1.3 Where to Find More Information

For more information about system messages, see “[Message Logging](#)” in the *ZENworks 10 Asset Management System Administration Reference*.


7.2 Creating a Watch List

If you have servers or workstations whose status you want to closely monitor, you can add them to the Watch List. The Watch List provides the following information:

- ♦ **Agent:** For servers and workstations, displays whether the device’s ZENworks Adaptive Agent is currently connected () or disconnected (.
- ♦ : Displays whether or not the object has any critical messages.
- ♦ **Type:** Displays an icon representing the object’s type. For example, a device might have a  icon to show that it is a server. You can mouse over the icon to see a description.
- ♦ **Name:** Displays the object’s name. You can click the name to go to the object’s message log.

To add a device to the Watch List:

- 1 In ZENworks Control Center, click the *Home* tab.



- 2 In the Watch List panel, click *Add > Device*.
 - 3 In the selection dialog box, select the desired object, then click *OK* to add it to the Watch List.
- For example, if you are adding servers, browse for and select a server.


Objects remain in the Watch List until you remove them.

7.3 Generating Reports

ZENworks Asset Management uses ZENworks Reporting Server to generate reports for your Management Zone. You can use predefined reports or custom reports.

To access the reports:

- 1 In ZENworks Control Center, click the *Reports* tab.



- 2 In the ZENworks Reporting Server panel, click *ZENworks Reporting Server InfoView* to launch the ZENworks Reporting Server InfoView. The ZENworks Reporting Server InfoView page is displayed with initial view as *Document List*.

The following table explains the various tasks you can perform in the ZENworks Reporting Server InfoView.

Task	Steps
Generate a predefined report	<ol style="list-style-type: none"> 1. Navigate the <code>Predefined Reports</code> folder until you locate the report definition on which you want to generate a report. 2. Click <i>Actions > Schedule</i>, or right-click the report, then select <i>Schedule</i>.
Generate a custom report	<ol style="list-style-type: none"> 1. In the InfoView toolbar, click <i>New > Web Intelligence Document</i>. The <i>Universe</i> pane is displayed. 2. In the <i>Data</i> tab, navigate to the universe object for which you want to create a report, and drag the object to the right pane. 3. Click <i>Run Query</i>. 4. Save the report in the <code>Custom Reports</code> folder.
View the earlier instances of a report	<ol style="list-style-type: none"> 1. Navigate the <code>Predefined Reports</code> or the <code>Custom Reports</code> folder until you locate the report whose earlier instances you want to view. 2. Click <i>Actions > History</i>, or right-click the report, and select <i>History</i>.
View the latest instance of a report	<ol style="list-style-type: none"> 1. Navigate the <code>Predefined Reports</code> or the <code>Custom Reports</code> folder until you locate the report whose latest instances you want to view. 2. Click <i>Actions > View Latest Instance</i>, or right-click the report, and select <i>View Latest Instance</i>.
View the properties of a report	<ol style="list-style-type: none"> 1. Navigate the <code>Predefined Reports</code> or the <code>Custom Reports</code> folder until you locate the report whose properties you want to view. 2. Click <i>Actions > Properties</i>, or right-click the report and select <i>Properties</i>.

You can also use the `report-generate-now` command, as well as other report commands, in the `zman` utility to manage reports. For more information, see “[Report Commands](#)” in the *ZENworks 10 Asset Management Command Line Utilities Reference*.

For more information about reporting, see the *ZENworks 10 Asset Management System Reporting Reference*.

