

ZENworks Reporting Server Installation Guide

Novell® ZENworks® 11

Support Pack 1

August 08, 2011

www.novell.com



Legal Notices

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2008-2011 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc.
1800 South Novell Place
Provo, UT 84606
U.S.A.
www.novell.com

Online Documentation: To access the latest online documentation for this and other Novell products, see the [Novell Documentation Web page \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

Novell Trademarks

For Novell trademarks, see [the Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

About This Guide	5
1 Minimum Requirements	7
1.1 ZENworks Reporting Server Requirements	7
1.2 Installation User Requirements	8
1.3 Web Browser Requirements	9
2 Installing ZENworks Reporting Server	11
2.1 Understanding What the ZENworks 11 SP1 Reporting Server Installation Does	11
2.2 Preinstallation Tasks	12
2.2.1 Verifying That the Minimum Requirements Have Been Met	12
2.2.2 Performing a Backup of Reports before Decommissioning an Existing Instance of ZENworks Reporting Server	12
2.2.3 Meeting the Hostname and Network Requirements in Linux	13
2.2.4 Creating an Installation DVD from the ISO Download	13
2.3 Installing ZENworks Reporting Server	13
2.3.1 Installation Information	14
2.3.2 Installer Logs	16
2.3.3 ZENworks Reporting Server Paths	16
2.3.4 ZENworks Reporting Server Version	17
2.4 Working With a Firewall	17
2.4.1 Specifying the Firewall Rules	17
2.5 Post-Installation Tasks	18
2.5.1 Restoring the Archived Data from the Decommissioned Device	18
2.5.2 Uninstalling a Decommissioned ZENworks Reporting Server	18
2.5.3 Closing Unnecessary Ports	18
2.5.4 Upgrading Apache Tomcat	18
3 Uninstalling ZENworks Reporting Server	21
3.1 Uninstalling ZENworks Reporting Server in the GUI Mode	21
3.2 Uninstalling ZENworks Reporting Server in the Command Line Mode	21
3.3 Uninstalling ZENworks Reporting Server in the Silent Mode	22
3.4 Uninstalling ZENworks Reporting Server by Using Windows Add or Remove Programs	22
3.5 Post Uninstallation Task	22
A Troubleshooting ZENworks Reporting Server Installation	23
A.1 ZENworks Reporting Server Error Messages	23
A.2 ZENworks Reporting Server Troubleshooting Strategies	24
B Documentation Updates	31
B.1 August 08, 2011: 11 SP1	31

About This Guide

This *Reporting Server Installation Guide* includes information to help you successfully install Novell ZENworks 11 SP1 Reporting Server. The information in this guide is organized as follows:

- ♦ Chapter 1, “Minimum Requirements,” on page 7
- ♦ Chapter 2, “Installing ZENworks Reporting Server,” on page 11
- ♦ Chapter 3, “Uninstalling ZENworks Reporting Server,” on page 21
- ♦ Appendix A, “Troubleshooting ZENworks Reporting Server Installation,” on page 23

Audience

This guide is intended for ZENworks Reporting Server administrators.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation.

Additional Documentation

ZENworks Reporting Server is supported by other documentation (in both PDF and HTML formats) that you can use to learn about and implement the product. For additional documentation, see the [ZENworks 11 SP1 documentation Web site \(http://www.novell.com/documentation/zenworks11/\)](http://www.novell.com/documentation/zenworks11/).

Minimum Requirements

1

The ZENworks 11 SP1 Reporting Server installation installs ZENworks Reporting Server for custom ZENworks infrastructure reporting.

The following sections provide the minimum hardware and software requirements for ZENworks Reporting Server:

- ♦ [Section 1.1, “ZENworks Reporting Server Requirements,” on page 7](#)
- ♦ [Section 1.2, “Installation User Requirements,” on page 8](#)
- ♦ [Section 1.3, “Web Browser Requirements,” on page 9](#)

1.1 ZENworks Reporting Server Requirements

You must install ZENworks Reporting Server on an existing ZENworks 11 SP1 Primary Server. You can have only one instance of ZENworks Reporting Server in a Management Zone.

The server where you install ZENworks Reporting Server software must meet the following minimum requirements:

Item	Requirements	Additional Details
Operating System	<p>Windows:</p> <ul style="list-style-type: none">♦ Windows Server 2003 SP1 / SP2 x86, x86_64 (Enterprise and Standard editions)♦ Windows Server 2008 SP1 / SP2 x86, x86_64 (Enterprise and Standard editions)♦ Windows Server 2008 R2 x86_64 (Enterprise and Standard editions) <p>Linux:</p> <ul style="list-style-type: none">♦ SUSE Linux Enterprise Server 10 (SLES 10) SP3 x86, x86_64 (Intel and AMD Opteron processors)♦ SLES 11 x86, x86_64 (Intel and AMD Opteron processors)♦ SLES 11 SP1 x86, x86_64 (Intel and AMD Opteron processors)♦ Open Enterprise Server 2 (OES 2) SP2 (Linux) x86, x86_64♦ Red Hat Enterprise Linux 5.0 / 5.3 / 5.4/5.5 x86, x86_64	<p>All the Core and Data Center Editions of Windows Server 2003 and Windows Server 2008 are not supported as Primary Server platforms. Windows Server 2008 Core is not supported because it does not support the .NET Framework.</p> <p>If you are installing ZENworks Reporting Server on a SUSE Linux Enterprise Server (SLES) 64-bit platform, make sure to install the libstdc++33-32bit package by using the SLES 64-bit media.</p>

Item	Requirements	Additional Details
Hardware	RAM: 3 GB minimum Disk Space: 8 GB minimum	On Windows, ensure that you have at least 8 GB of free disk space on the drive on which the operating system has been installed if the <code>TEMP</code> environment variable is not set on the same drive. If the <code>TEMP</code> environment variable is set on the same drive on which the operating system has been installed, ensure that you have at least 13 GB of free disk space on the drive.
TCP Ports	3306	Used by the MySQL database embedded in ZENworks Reporting Server
	6400	Used by the Central Management Server in ZENworks Reporting Server
	6410	Used by the Server Intelligence Agent in ZENworks Reporting Server
	6420	Auditing port in ZENworks Reporting Server
	6430	Used by the CMS Server of BusinessObjects Enterprise to set its request port parameter
	8080	Non secure port used by BOE's tomcat
	8443	Secure port used by BOE's tomcat
	8006	Shutdown port used by BOE's tomcat.

1.2 Installation User Requirements

The user running the installation program must have administrator privileges on the device. For example:

- ♦ **Windows:** Log in as a Windows administrator.
- ♦ **Linux:** Log in as a non-root user, use the `sux` command to elevate your privileges to `root`, then run the installation program.

1.3 Web Browser Requirements

The Web browsers supported by BusinessObjects Enterprise XI 3.1 (ZENworks Reporting Server) include the following:

Windows Operating System

Table 1-1 Supported Web Browsers for Windows Operating Systems

Browser OS	Browser
Windows	<ul style="list-style-type: none">♦ Internet Explorer 8.0♦ Firefox 3.0♦ Firefox 3.5

Linux Operating System

Table 1-2 Supported Web Browsers for Linux Operating Systems

Browser OS	Browser
Linux	<ul style="list-style-type: none">♦ Firefox 3.0♦ Firefox 3.5♦ Firefox 5.0

NOTE: The Firefox 4.0 browser is not supported.

For more information on the minimum browser requirements, see SAP BusinessObjects Enterprise XI 3.1 SP3 documentation for Windows and Linux supported platforms.

Installing ZENworks Reporting Server

2

Perform the tasks in the following sections to install ZENworks 11 SP1 Reporting Server:

- ♦ [Section 2.1, “Understanding What the ZENworks 11 SP1 Reporting Server Installation Does,” on page 11](#)
- ♦ [Section 2.2, “Preinstallation Tasks,” on page 12](#)
- ♦ [Section 2.3, “Installing ZENworks Reporting Server,” on page 13](#)
- ♦ [Section 2.4, “Working With a Firewall,” on page 17](#)
- ♦ [Section 2.5, “Post-Installation Tasks,” on page 18](#)

2.1 Understanding What the ZENworks 11 SP1 Reporting Server Installation Does

ZENworks 11 SP1 Reporting Server uses the BusinessObjects Reporting Engine XI R3.1 SP3 engine and is installed from a separate installation media.

You cannot upgrade from ZENworks 10 SP3 Reporting Server to ZENworks 11 SP1 Reporting Server. You can only upgrade from ZENworks 11 Reporting Server to ZENworks 11 SP1 Reporting Server.

For more information, see “[Upgrading the ZENworks Reporting Server](#)” in the *ZENworks 11 SP1 Upgrade Guide*.

You can install ZENworks Reporting Server in the languages supported by ZENworks 11 SP1. The installation time depends on the number of languages that you have selected.

You can install ZENworks Reporting Server by using any of the following installation methods:

- ♦ **Graphical User Interface:** A graphical user interface (GUI) installation program that works with both Windows and Linux servers is provided on the installation CD.
- ♦ **Command Line:** A command line installation is available only for Linux servers.
- ♦ **Silent Mode:** A silent mode installation does not require any user intervention. You must edit the silent mode configuration file and run the installer with a switch to launch the silent mode installation.

For more information on how to install ZENworks Reporting Server, see [Section 2.3, “Installing ZENworks Reporting Server,” on page 13](#).

2.2 Preinstallation Tasks

Perform the following applicable tasks, then continue with [Section 2.3, “Installing ZENworks Reporting Server,”](#) on page 13:

- ♦ [Section 2.2.1, “Verifying That the Minimum Requirements Have Been Met,”](#) on page 12
- ♦ [Section 2.2.2, “Performing a Backup of Reports before Decommissioning an Existing Instance of ZENworks Reporting Server,”](#) on page 12
- ♦ [Section 2.2.3, “Meeting the Hostname and Network Requirements in Linux,”](#) on page 13
- ♦ [Section 2.2.4, “Creating an Installation DVD from the ISO Download,”](#) on page 13

2.2.1 Verifying That the Minimum Requirements Have Been Met

- ♦ Make sure that short MS-DOS (also called 8.3) style naming convention is available for the installation location of the ZENworks 11 SP1 Server. By default, 8.3 is enabled on the device. For more information on how to enable 8.3 see, [Microsoft documentation \(http://technet.microsoft.com/en-us/library/cc959352.aspx\)](http://technet.microsoft.com/en-us/library/cc959352.aspx).

For more information on the installation path of the ZENworks 11 SP1 Server, see “[Installation Information](#)” in the *ZENworks 11 SP1 Installation Guide*.

- ♦ Make sure that the device where you want to install the server software fulfills the necessary requirements. For more information, see [Chapter 1, “Minimum Requirements,”](#) on page 7.
- ♦ Make sure that ports 6400, 3306, 6410, 6430, 6420, 8080, 8443, and 8006 are free. If these ports are busy, you are prompted to specify alternative ports on which to install ZENworks Reporting Server.

If the ports are blocked by a firewall, you must enable the firewall. For more information, see [Section 2.4, “Working With a Firewall,”](#) on page 17.

- ♦ Make sure that the server is connected to the network.
- ♦ Make sure that the Novell ZENworks Server, the Novell ZENworks Loader, and the Novell ZENworks Database services are running.
- ♦ If you are installing ZENworks Reporting Server on a SUSE Linux Enterprise Server (SLES) 10 SP3 64-bit platform, make sure to install the libstdc++33-32bit package by using the SLES 10 SP3 64-bit media.

2.2.2 Performing a Backup of Reports before Decommissioning an Existing Instance of ZENworks Reporting Server

There can be only one instance of ZENworks Reporting Server in a Management Zone. If you want to install a new instance of ZENworks Reporting Server in the same Management Zone, you must decommission the existing instance of ZENworks Reporting Server, and install the new instance, using the ZENworks 11 SP1 installer. The installer will decommission the existing instance from the Management Zone and install a new instance. For more information, see “[Prerequisites](#)” on page 15.

Prior to decommissioning the existing instance of the ZENworks Reporting Server, you need to ensure you backup the reports from your existing instance. This is because the existing instance of ZENworks Reporting Server ceases to work after the new installation is complete, and you cannot retrieve any reports. You can restore the archived reports to the new instance of ZENworks Reporting Server.

To save reports and user rights, use the following command:

```
zman rpsv <destination_folder>
```

For more information on how to retrieve the archived reports, see [Section 2.5.1, “Restoring the Archived Data from the Decommissioned Device,”](#) on page 18.

2.2.3 Meeting the Hostname and Network Requirements in Linux

Your Linux server must have a fixed hostname before you run the installation script. You must have root privileges to set or modify this information on your system. For more information, see the Linux system documentation.

IMPORTANT: Before you install ZENworks 11 SP1 Reporting Server on an RHEL server, make sure you have the machine’s configured IP address and FQDN entry in the /etc/hosts file, before the localhost IP address and FQDN entry.

2.2.4 Creating an Installation DVD from the ISO Download

If you obtained the ZENworks 11 SP1 Reporting Server software as an ISO image download, you need to create separate installation DVDs for Windows and Linux to install ZENworks Reporting Server on these platforms.

- 1 Download the ZENworks 11 Reporting Server installation ISO image from the [Novell Web site](http://www.novell.com/) (<http://www.novell.com/>) and copy it to a temporary location on your Windows or Linux device.
- 2 Burn the ISO image to a DVD.

On Linux, optionally, you can simply run the installation program from the ISO mount point, instead of burning the DVD.

NOTE: On Linux devices, ensure that the pathname to the ZENworks Reporting Server installer should not contain any blank spaces in it.

2.3 Installing ZENworks Reporting Server

- 1 Start the ZENworks Reporting Server installation program by using one of the following methods:
 - ♦ **Graphical User Interface (GUI) Installation**
 1. On the installation server, insert the *Novell ZENworks 11 SP1 with Reporting Server* DVD for Windows.

On a Windows device, the installation begins automatically after inserting the DVD. You can also select the language from the installation page that appears. If the installation does not begin automatically, run `setup.exe` from the root after inserting the DVD.

On a Linux device, mount the DVD, then run `sh /media/cdrom/setup.sh`.

♦ **Command Line Installation (Linux only)**

1. On the installation server, insert the *Novell ZENworks 11 SP1 with Reporting Server* DVD for Linux.
2. Mount the DVD.
3. To start a command line installation to a directory where all (including “others”) have read and execute access, either mount the DVD or copy the DVD’s files to a temporary location other than the `/root` directory.

Ensure that the copied files and their parent directories have read and execute access for all the users (including “others”).

4. Run the following command:

```
/mount_location/setup.sh -e
```

♦ **Silent Mode Installation**

1. Create a silent install configuration file by using the following command:

```
setup.exe/setup.sh -s
```

2. Open the silent install configuration file in a text editor.
3. Search for `ADMINISTRATOR_PASSWORD=`.
4. Replace `$lax.nl.env.ADMIN_PASSWORD$` with the actual password.

For example, if the password is `novell`, then the entry will be as follows:

```
ADMINISTRATOR_PASSWORD=novell.
```

5. Save the silent install configuration file and exit the editor.
6. Run the silent install configuration file by using the following command:

```
setup.exe/setup.sh -s -f path_to_the_silent_install_file
```

- 2 During installation, refer to the information in [Table 2-1, “Installation Information,” on page 15](#) for details on the installation data that you need to know.

If you are using the GUI installation, you can also click the *Help* button for similar information.

For the command line method, you can type back and press Enter to return to a previous installation option to make changes.

In either case, part of completing the installation process is for the database to be updated, which causes high CPU utilization during that process. This can cause the services to start up slowly.

IMPORTANT: You can install ZENworks 11 SP1 ZENworks Reporting Server only through media. You cannot install it by mapping to a network drive.

2.3.1 Installation Information

The information you need is listed in the order of the installation flow.

Table 2-1 *Installation Information*

Installation Information	Explanation
Pre-installation Details	<ul style="list-style-type: none"> ♦ You are prompted to select the language in which to run the ZENworks 11 SP1 Reporting Server installer. Select the language and click <i>OK</i>. ♦ A brief introduction about the ZENworks 11 SP1 Reporting Server is displayed. Click <i>Next</i>. ♦ The License Agreement screen is displayed. Click <i>Agree</i> and then click <i>Next</i>.
Prerequisites	<ul style="list-style-type: none"> ♦ The installer checks to see if a ZENworks 11 SP1 Configuration Management Server is installed on the device. ♦ The installer checks to see if an instance of ZENworks Reporting Server exists in the zone. If it exists, the installer prompts to decommission the existing instance of ZENworks Reporting Server. For more information, see Section 2.2.2, “Performing a Backup of Reports before Decommissioning an Existing Instance of ZENworks Reporting Server,” on page 12. ♦ The ZENworks 11 SP1 Reporting Server installer checks if ZENworks 11 Reporting Server is installed on the device. If yes, you are prompted to upgrade to ZENworks 11 SP1 Reporting Server. For more information, see the “Upgrading the ZENworks Reporting Server” section in the ZENworks 11 SP1 Upgrade Guide. ♦ The installer prompts for username and password. Specify the super administrator’s username and password for the ZENworks zone. If the credentials are correct, the installer checks for other prerequisites such as available disk space, operating system, and system architecture on the device. ♦ If the required prerequisites are not met, you cannot continue with the installation. The prerequisites that are not met are displayed (GUI) or listed (command line).
Installation Summary	<ul style="list-style-type: none"> ♦ The Language Selection screen appears. Select the language in which you want to use the ZENworks 11 SP1 Reporting Server. <p>The installation time depends on the number of language selected.</p> <hr/> <p>IMPORTANT: After you install ZENworks Reporting Server, you cannot change the Certificate Authority (CA) type of the ZENworks Primary Server from Internal CA to External CA or vice-versa.</p> <hr/>
Pre-installation summary	<p>GUI Installation: To modify any information that you have entered up to this point, click <i>Previous</i>. Click <i>Install</i> to begin the installation.</p> <p>Click <i>Cancel</i> to exit the installation. No rollback occurs on cancelling the installation.</p> <p>Command Line Installation: To modify any information that you have entered up to this point, type <i>back</i> and press Enter.</p> <p>Press Ctrl+C to exit the installation. No rollback occurs on cancelling the installation.</p>
Installation completion	A confirmation is displayed upon successfully completing the installation.

IMPORTANT: Restart the ZENworks Reporting Server machine after you install ZENworks Reporting Server.

2.3.2 Installer Logs

The Installer logs are stored in the following location:

On Windows: %zenworks_home%\logs\

On Linux: /var/opt/novell/log/zenworks/

The log files that ZENworks Reporting Server creates in these locations are:

ZENworks Reporting Server_date time.log.xml

wdeploy-AnalyticalReporting-datetime.log

wdeploy-CrystalReports-datetime.log

wdeploy-InfoViewApp-datetime.log

wdeploy-InfoViewAppActions-datetime.log

wdeploy-OpenDocument-2011-datetime.log

wdeploy-PlatformServices-datetime.log

2.3.3 ZENworks Reporting Server Paths

After the successful installation of ZENworks Reporting Server, the ZENworks Reporting server is installed within the ZENworks 11 SP1 install folder:

- ♦ **For Windows:**

%ZENWORKS_HOME%\share\boe

- ♦ **For Linux:**

\$ZENWORKS_HOME%/share/boe

For more information, see “Installation Information” in the ZENworks 11 SP1 Installation Guide.

2.3.4 ZENworks Reporting Server Version

- ♦ **On Linux:**

- ♦ The version of the zone when ZENworks Reporting Server was first installed is available in the `ZENworksReportingServerVersion.txt` file located in the `/opt/novell/zenworks/share/boe/version` # directory.
- ♦ The version of the currently published reports and universe is available in the `ZENworksReportingServiceComponentsVersion.txt` file located in the `/opt/novell/zenworks/share/boe-publish/version` directory.

- ♦ **On Windows:**

- ♦ The version of the zone when ZENworks Reporting Server was first installed is available in the `ZENworksReportingServerVersion.txt` file located in the `%ZENWORKS_HOME%\share\boe\version` # directory.
- ♦ The version of the currently published reports and universe is available in the `ZENworksReportingServiceComponentsVersion.txt` file located in the `%ZENWORKS_HOME%\share\boe-publish\version` directory.

2.4 Working With a Firewall

ZENworks Reporting Server works with firewall systems to provide reporting across intranets and the Internet without compromising network security.

This section provides information about how to configure ZENworks Reporting Server in a packet filtering firewall environment. For detailed information about how ZENworks Reporting Server works in other types of firewall environments, see the *BusinessObjects Enterprise XI Release 3 SP3 Deployment and Configuration Guide* (<http://support.businessobjects.com/documentation/default.asp>).

2.4.1 Specifying the Firewall Rules

If there is a firewall between ZENworks Reporting Server and other ZENworks Primary Servers, you must specify the inbound access rules. For more details on how to specify these rules, see the firewall documentation.

The following table lists the inbound access rules:

Table 2-2 *Inbound Access Rules*

Source Device	Port	Destination Device	Port	Action
ZENworks Primary Server	Any	ZENworks Reporting Server (CMS)	6400	Allow
ZENworks Primary Server	Any	ZENworks Reporting Server (CMS)	6430	Allow
ZENworks Primary Server	Any	ZENworks Reporting Server (other ZENworks Reporting Server service)	6430	Allow
Any machine	Any	ZENworks Reporting Server (CMS)	Any	Reject

Source Device	Port	Destination Device	Port	Action
Any	Any	ZENworks Reporting Server (other ZENworks Reporting Server service)	Any	Reject

2.5 Post-Installation Tasks

- ♦ [Section 2.5.1, “Restoring the Archived Data from the Decommissioned Device,” on page 18](#)
- ♦ [Section 2.5.2, “Uninstalling a Decommissioned ZENworks Reporting Server,” on page 18](#)
- ♦ [Section 2.5.3, “Closing Unnecessary Ports,” on page 18](#)
- ♦ [Section 2.5.4, “Upgrading Apache Tomcat,” on page 18](#)

2.5.1 Restoring the Archived Data from the Decommissioned Device

To restore the backed-up data from the decommissioned device, use the following command:

```
zman rpld <source_folder>
```

For more information on the `save` and `restore` commands, see [“Report Commands”](#) in the *ZENworks 11 SP1 Command Line Utilities Reference*.

2.5.2 Uninstalling a Decommissioned ZENworks Reporting Server

You can use the ZENworks Reporting Server Uninstaller to uninstall a decommissioned ZENworks Reporting Server.

For more information on how to uninstall ZENworks Reporting Server, see [Chapter 3, “Uninstalling ZENworks Reporting Server,” on page 21](#).

2.5.3 Closing Unnecessary Ports

You can close the following ports after you install the ZENworks 11 SP1 Reporting Server:

- ♦ non-SSL port - 8080
- ♦ shutdown port - 8006

NOTE: These ports are opened when you install ZENworks 11 SP1 Reporting Server. However, they are not required for ZENworks Reporting Server to function properly.

2.5.4 Upgrading Apache Tomcat

ZENworks Reporting Server now uses the Apache Tomcat version shipped with BusinessObjects Enterprise. The default version is Tomcat 5.5.20.

If you find any known vulnerabilities in the current Tomcat version and you want to upgrade to the latest patch (Tomcat 5.5.x):

- 1** Stop Tomcat through the BusinessObjects Windows Central Configuration Management, and verify that no Tomcat 5.5 processes are running in the Windows task manager.
- 2** Rename C:\Program Files\Business Objects\Tomcat55 as C:\Program Files\Business Objects\Tomcat55.bak.
- 3** Download the Tomcat 5.5.x core zip file from the Apache Web site to C:\Program Files\Business Objects\.
- 4** Unzip the zip file to C:\Program Files\Business Objects\Tomcat55.
When this file is unzipped, a new folder named apache-tomcat-5.5.x is created.
- 5** Rename the apache-tomcat-5.5.x folder as Tomcat55.
- 6** Open the Windows command (DOS) prompt and change the directories to C:\Program Files\Business Objects\deployment
- 7** At the command prompt run wdeploy.bat tomcat55 deployall.
This command deploys all the webapps to the new Tomcat and wdeploy ends with Build Successful.
- 8** Start Tomcat through the Windows Central Configuration Manager.
- 9** Test the ZENworks Reporting Server InfoView.

Uninstalling ZENworks Reporting Server

3

On a Primary Server in a Management Zone, you must first uninstall ZENworks Reporting Server before you uninstall ZENworks Configuration Management.

Uninstalling ZENworks Reporting Server deletes all the reporting rights specified within the roles and those that are assigned to the administrators.

NOTE: ZENworks Reporting Server is uninstalled in the same mode that it was installed in.

For example, if you installed ZENworks Reporting Server by using the command line mode, then the uninstallation program uninstalls the server in the command line mode only.

- ♦ [Section 3.1, “Uninstalling ZENworks Reporting Server in the GUI Mode,” on page 21](#)
- ♦ [Section 3.2, “Uninstalling ZENworks Reporting Server in the Command Line Mode,” on page 21](#)
- ♦ [Section 3.3, “Uninstalling ZENworks Reporting Server in the Silent Mode,” on page 22](#)
- ♦ [Section 3.4, “Uninstalling ZENworks Reporting Server by Using Windows Add or Remove Programs,” on page 22](#)
- ♦ [Section 3.5, “Post Uninstallation Task,” on page 22](#)

3.1 Uninstalling ZENworks Reporting Server in the GUI Mode

- 1 Start the uninstallation program.

On Windows, run the following command:

```
%ZENWORKS_HOME%\bin\zrsuninstall.exe
```

On Linux, run the following command:

```
/opt/novell/zenworks/bin/zrsuninstall
```

The Uninstall Reporting Server page is displayed.

- 2 Click *Uninstall*.
- 3 The uninstaller checks for an active ZENworks Reporting Server in the zone.
- 4 Click *Yes* on the prompt that is displayed.
The uninstallation begins.
- 5 In the Uninstall Complete page, click *Done*.

3.2 Uninstalling ZENworks Reporting Server in the Command Line Mode

- 1 Start the uninstallation program.

On Linux, run the following command:

```
/opt/novell/zenworks/bin/zrsuninstall
```

The uninstallation begins.

- 2 Follow the on-screen prompts to complete the uninstallation process.

3.3 Uninstalling ZENworks Reporting Server in the Silent Mode

- 1 Start the uninstallation program.

On Windows, run the following command:

```
%ZENWORKS_HOME%/bin/zrsuninstall.exe
```

On Linux, run the following command:

```
/opt/novell/zenworks/bin/zrsuninstall
```

On a Windows device, you can view the logs in the Windows - %ZENWORKS_HOME%/logs/ZRSuninstall_dd_mm_yyyy_hh.mm.ss.log file. On a Linux device, you can view the logs in the linux - /var/opt/novell/log/zenworks/ZRSuninstall_dd_mm_yyyy_hh.mm.ss.log file.

3.4 Uninstalling ZENworks Reporting Server by Using Windows Add or Remove Programs

- 1 On the desktop, click *Start > Settings > Control Panel > Add or Remove Programs*.
- 2 In the Add or Remove Programs window, select *ZENworks Reporting Server*, then click *Remove*.

3.5 Post Uninstallation Task

After you uninstall ZENworks Reporting Server on a Linux platform, there may be some Business Objects Enterprise files that are not removed from the device. If these files have not been removed, you need to manually remove them. The Business Objects Enterprise files that should be removed include the following:

- ♦ /etc/init.d/rc3.d/S12BobjEnterprise120
- ♦ /etc/init.d/rc3.d/K10BobjEnterprise120
- ♦ /etc/init.d/rc5.d/S12BobjEnterprise120
- ♦ /etc/init.d/rc5.d/K10BobjEnterprise120

Troubleshooting ZENworks Reporting Server Installation

A

The following sections provide solutions to the problems you might encounter while working with Novell ZENworks 11 SP1 Reporting Server:

- ♦ [Section A.1, “ZENworks Reporting Server Error Messages,” on page 23](#)
- ♦ [Section A.2, “ZENworks Reporting Server Troubleshooting Strategies,” on page 24](#)

A.1 ZENworks Reporting Server Error Messages

This section contains detailed explanations of some of the error messages you might encounter when you are using ZENworks Reporting Server.

- ♦ [“ZENworks Reporting Server Uninstall Failed” on page 23](#)
- ♦ [“Operating System Requirements Failed” on page 23](#)
- ♦ [“This device is an active Reporting Server. If you uninstall the ZENworks 11 SP1 Reporting Server, then the entries are removed from the database” on page 23](#)

ZENworks Reporting Server Uninstall Failed

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Possible Cause: The Novell ZENworks Loader service has failed to restart at the end of the uninstallation process.

Action: Manually restart the Novell ZENworks Loader service.

Operating System Requirements Failed

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Possible Cause: This error message occurs if ZENworks Reporting Server is installed on Windows Server 2008 R2 platform and you are installing the Oracle 10g R2 client.

Action: Select the check box next to the *Operating Systems Requirements* field to change the state from Operating System Requirements failed to User Verified, then continue with the installation.

This device is an active Reporting Server. If you uninstall the ZENworks 11 SP1 Reporting Server, then the entries are removed from the database

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Explanation: This is an incorrect message that is displayed during the uninstallation of an older version of ZENworks Reporting Server in a ZENworks 11 SP1 environment.

Action: Ignore the message. Click *OK* to close the dialog box and continue with the uninstallation process.

A.2 ZENworks Reporting Server Troubleshooting Strategies

This section provides solutions to problems you might encounter when using ZENworks Reporting Server.

- ♦ “ZENworks Reporting Server installation fails on a 64-bit Windows device that is using an Oracle database” on page 24
- ♦ “How do I enable debug logging for ZENworks Reporting Server services?” on page 25
- ♦ “Where do I find the BusinessObjects Enterprise log files?” on page 25
- ♦ “Where do I find ZENworks Reporting Server log files?” on page 25
- ♦ “The ZENworks Reporting Server installation on a virtual machine might fail when you use the ZCM_REPORTING_10.x.0.iso file mounted on the host machine as a CD-ROM on that virtual machine” on page 26
- ♦ “A message indicating that ZENworks Reporting Server cannot be deleted appears even after uninstalling ZENworks Reporting Server” on page 26
- ♦ “A message indicating that ZENworks Reporting Server uninstallation process failed is displayed while uninstalling ZENworks Reporting Server” on page 26
- ♦ “Reporting Server uninstallation on Windows fails if another installation is in progress on the same device” on page 26
- ♦ “Reporting does not work on a Primary Server if the ZENworks database is an MS SQL Server database, and the authentication mode is Windows Authentication” on page 27
- ♦ “ZENworks Reporting Server installation on a Windows Server 2008 R2 device fails” on page 28
- ♦ “ZENworks Reporting Server installation on an RHEL server fails with error 'Unable to find Business Object daemon'” on page 28

ZENworks Reporting Server installation fails on a 64-bit Windows device that is using an Oracle database

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Possible Cause: The installation path specified for ZENworks Configuration Management might contain parentheses.

Action 1: If you want to install ZENworks Reporting Server on the same Primary Server:

- 1 Uninstall ZENworks Configuration Management from the Primary Server.
- 2 Install ZENworks Configuration Management to a customized location that does not contain any parentheses in the pathname. For more information, see “[Installation Information](#)” in the *ZENworks 11 SP1 Installation Guide*.

Action 2: If you want to install ZENworks Reporting Server on a different server:

- 1 On the new server, install ZENworks Configuration Management to a customized location that does not contain any parentheses in the pathname. For more information, see “[Installation Information](#)” in the *ZENworks 11 SP1 Installation Guide*.
- 2 Install ZENworks Reporting Server.

How do I enable debug logging for ZENworks Reporting Server services?

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Action: To enable the logs, see TID 3418069 in the [Novell Support Knowledgebase](http://support.novell.com/search/kb_index.jsp) (http://support.novell.com/search/kb_index.jsp).

Where do I find the BusinessObjects Enterprise log files?

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Action: You can find the ZENworks Reporting Server installation log files in the following locations:

On Windows:

```
%zenworks_home%\share\boe\Business Objects Enterprise  
120\logging\BOEInstall_0.log
```

On Linux:

```
/opt/novell/zenworks/share/boe/bobje/logging/install_timestamp.log
```

You can find the ZENworks Reporting Server trace files in the following locations:

On Windows:

```
%zenworks_home%\share\boe\Business Objects Enterprise  
120\logging
```

On Linux:

```
/opt/novell/zenworks/share/boe/bobje/logging/
```

Where do I find ZENworks Reporting Server log files?

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Action: If you have installed ZENworks Reporting Server through the Graphical User Interface (GUI) Installer, you can find all the installation logs at the following locations:

♦ On Windows:

```
%zenworks_home%\logs\ZENworks Reporting Server_date time.log.xml  
♦ %zenworks_home%\logs\wdeploy-date-time.log  
♦ %zenworks_home%\logs\ZENworks_Reporting_Install_CheckOracleClient_dd MMM_yyyy_HH-mm-ss.log
```

- ♦ **On Linux:**

```
/var/opt/novell/log/zenworks/ZENworks Reporting Server__date time.log.xml
```

- ♦ `/var/opt/novell/log/zenworks/wdeploy-date-time.log`
- ♦ `%zenworks_home%\logs\ZENworks_Reporting_Install_CheckOracleClient_dd_MMM_yyyy_HH-mm-ss.log`

The ZENworks Reporting Server installation on a virtual machine might fail when you use the ZCM_REPORTING_10.x.0.iso file mounted on the host machine as a CD-ROM on that virtual machine

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Action 1: Extract the `ZCM_REPORTING_10.x.0.iso` file to a directory on the virtual machine and run ZENworks Reporting Server installation from that directory.

Action 2: Burn the `ZCM_REPORTING_10.x.0.iso` file to a DVD and use it to install ZENworks Reporting Server on the virtual machine.

A message indicating that ZENworks Reporting Server cannot be deleted appears even after uninstalling ZENworks Reporting Server

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Action: Ignore the message. Click *Done* to close the Uninstall Complete window.

A message indicating that ZENworks Reporting Server uninstallation process failed is displayed while uninstalling ZENworks Reporting Server

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Explanation: This is an incorrect message that is displayed during the uninstallation process when the Novell ZENworks Loader service has failed to restart at the end of the uninstallation process.

Additionally, the ZENworks Reporting Server uninstall log file and the Service Message log file contain the following messages respectively:

- ♦ “[ERROR] [8/10/09 1:10:00 PM] [] [UNINSTALL] [ZRS Uninstall Failed with exceptioncom.novell.zenworks.configure.ConfigureException: 2]”
- ♦ “Failed to send RPC command to the zenloader process: settings.refresh” respectively.

Action: Manually restart the Novell ZENworks Loader service.

Reporting Server uninstallation on Windows fails if another installation is in progress on the same device

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Explanation: The following message is logged into the `%ZENWORKS_HOME%\logs\zrsuninstall.log` file:

```
ERROR_INSTALL_ALREADY_RUNNING
```

Action: Do the following:

- 1 Open the Windows Task Manager and stop all instances of `msiexec.exe` and `setup.exe`.
- 2 Uninstall ZENworks Reporting Server.

Reporting does not work on a Primary Server if the ZENworks database is an MS SQL Server database, and the authentication mode is Windows Authentication

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Explanation: The following error might be displayed while running the reports:

On Windows

A database error occurred. The database error text is:
[Microsoft][ODBC SQL Server Driver][SQL Server] Login failed
for user "NT
AUTHORITY\ANONYMOUS LOGON"..(WIS 10901)

On Linux

A database error occurred. The database error text is:
[DataDirect][ODBC SQL Server Driver][SQL Server]Login failed
for user zcm-db-user@company.com

Action: Do the following:

On Windows:

- 1 Provide Read permission to `%ZENWORKS_HOME%/conf/security` directory and Full Control permission to `%ZENWORKS_HOME%/share/boe` directory for the domain user account of the Windows server that hosts the ZENworks Configuration Management database. For a non-domain user, the username and password must be the same on the ZENworks Configuration Management Server database and ZENworks Reporting Server. You must also provide the Read and Full Control permission to the non-domain user.
- 2 Edit the properties of ZENworks Reporting Server Services on the ZENworks Server:
- 3 From the desktop *Start* menu, click *All Programs > ZENworks Reporting Server > ZENworks Reporting Server > Central Configuration Manager*. The Central Configuration Manager window is displayed.
- 4 Right-click *Server Intelligence Agent (ZENReporting)*, then click *Stop*.
- 5 Right-click *Server Intelligence Agent (ZENReporting)*, then click *Properties*.
The Server Intelligence Agent (ZENReporting) Properties window is displayed.
- 6 In the Log On As panel, deselect *System Account*, then specify the username and password of the domain account of the Windows server that hosts the ZENworks Configuration Management database.

- 7 Click *OK*.
- 8 Right-click *Server Intelligence Agent (ZENReporting)*, then click *Start*.

On Linux:

- 1 Set up the MSSQL server to function in MixedMode.
- 2 In MSSQL, create a local database account with full rights to the ZENworks database.
- 3 On the ZENworks Reporting Server, modify the following two files: `dmaccounts.properties` and `dmamappings.properties`. Replace the Active Directory user name and password with the local database user name and password created in [Step 2](#).
- 4 Restart the services using the following command: `novell-zenworks-configure -c Start`
- 5 Access ZCC and verify if it is working.
- 6 Update the BOE to view the updated config files using the following command: `novell-zenworks-configure -c UpdateBOE`
- 7 Verify if reports for ZENworks Reporting Server now run in ZENworks Control Center.

ZENworks Reporting Server installation on a Windows Server 2008 R2 device fails

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Explanation: If the IP Helper service is running on a Windows Server 2008 R2 device, the ZENworks Reporting Server Installation fails.

Action: Disable the IP Helper service:

- 1 Click *Start > Settings > Control Panel > Administrative Tools > Services*.
- 2 Right-click *IP Helper*, then select *Properties*.
- 3 Select *Stop* to stop the service.
- 4 In the *Startup Type* drop-down list, select *Disabled*.
- 5 Click *Apply*.
- 6 Install ZENworks Reporting Server.

For more information on installing ZENworks Reporting Server, see the [Reporting Server Installation Guide \(http://www.novell.com/documentation/zenworks11/zen11_installation_reportingserver/data/bookinfo.html\)](http://www.novell.com/documentation/zenworks11/zen11_installation_reportingserver/data/bookinfo.html).

ZENworks Reporting Server installation on an RHEL server fails with error 'Unable to find Business Object daemon'

Source: ZENworks 11 SP1; ZENworks Reporting Server.

Explanation: When ZENworks 11 SP1 Reporting Server is installed on an RHEL server, the installation fails, and displays an error message “Unable to find Business Object daemon”

Action: Before installation, in the `/etc/hosts` file, enter the machine's configured IP address and hostname entry in the beginning of the file, before the localhost IP address and hostname entry.

Documentation Updates

B

This section contains information on documentation content changes that were made in this *ZENworks Reporting Server Installation Guide* for Novell ZENworks 11 SP1. The information can help you to keep current on updates to the documentation.

The documentation for this product is provided on the Web in two formats: HTML and PDF. The HTML and PDF documentation are both kept up-to-date with the changes listed in this section.

If you need to know whether a copy of the PDF documentation that you are using is the most recent, the PDF document includes a publication date on the title page.

The documentation was updated on the following dates:

- ♦ [Section B.1, “August 08, 2011: 11 SP1,” on page 31](#)

B.1 August 08, 2011: 11 SP1

Location	Change
Section 2.2, “Preinstallation Tasks,” on page 12	Added the following section: Section 2.2.2, “Performing a Backup of Reports before Decommissioning an Existing Instance of ZENworks Reporting Server,” on page 12
Section 2.5, “Post-Installation Tasks,” on page 18	Added the following sections: <ul style="list-style-type: none">♦ Section 2.5.3, “Closing Unnecessary Ports,” on page 18♦ Section 2.5.4, “Upgrading Apache Tomcat,” on page 18
Appendix A, “Troubleshooting ZENworks Reporting Server Installation,” on page 23	Added new troubleshooting scenarios.

