

Novell ZENworks® Asset Management Migration Utility

10

www.novell.com

MIGRATION GUIDE

March 28, 2008



Novell®

Legal Notices

Novell, Inc., makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc., makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2007–2008 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc., has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the [Novell Legal Patents Web page \(http://www.novell.com/company/legal/patents/\)](http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc.
404 Wyman Street, Suite 500
Waltham, MA 02451
U.S.A.
www.novell.com

Online Documentation: To access the latest online documentation for this and other Novell products, see the [Novell Documentation Web page \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

Novell Trademarks

For Novell trademarks, see [the Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

About This Guide	7
1 Planning Your Migration to ZENworks Configuration Management	9
1.1 Before You Begin	9
2 Using the Novell ZENworks Asset Management Migration Utility	11
2.1 Overview	11
2.2 Installing the ZENworks Asset Management Migration Utility	11
2.3 Selecting the Migration Source	12
2.4 Selecting the Migration Destination	12
2.5 Using the Migration Console to Migrate Objects	13
2.5.1 Migrating Inventory Data	13
2.5.2 Migrating Local Product Definitions	13
3 Understanding the Migration Console	15
3.1 Select Objects to Migrate Tab	15
3.2 Items to Migrate Tab	15
3.3 Migration Status Tab	16
3.4 Migration History Tab	16
3.5 Migrated Objects Tab	16
3.6 Select ZAM Database Field	16
3.7 Select Zone Field	16
3.8 Start Migration Button	17
3.9 Cancel Button	17

About This Guide

This *Novell ZENworks Asset Management Migration Utility Migration Guide* includes information to help you successfully migrate selected inventory data from ZENworks® Asset Management 7.5 to an installed Novell® ZENworks 10 Configuration Management system. The information in this guide is organized as follows:

- ♦ Chapter 1, “Planning Your Migration to ZENworks Configuration Management,” on page 9
- ♦ Chapter 2, “Using the Novell ZENworks Asset Management Migration Utility,” on page 11
- ♦ Chapter 3, “Understanding the Migration Console,” on page 15

Audience

This guide is intended for ZENworks Configuration Management administrators.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to the [Novell Documentation Feedback site \(http://www.novell.com/documentation/feedback.html\)](http://www.novell.com/documentation/feedback.html) and enter your comments there.

Additional Documentation

ZENworks Configuration Management is supported by other documentation (in both PDF and HTML formats) that you can use to learn about and implement the product. For additional documentation, see the [ZENworks 10 Configuration Management documentation \(http://www.novell.com/documentation/zcm10/index.html\)](http://www.novell.com/documentation/zcm10/index.html).

Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol (®, ™, etc.) denotes a Novell trademark. An asterisk (*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux*, should use forward slashes as required by your software.

Planning Your Migration to ZENworks Configuration Management

1

Novell® ZENworks® Configuration Management provides the ZENworks Asset Management Migration utility that allows you to migrate your local products and enterprise inventory data from ZENworks Asset Management 7.5 to ZENworks Configuration Management.

The ZENworks Asset Management Migration utility is provided with Configuration Management. You copy and install it to your workstation from an executable file that resides on your Primary Server. The utility consists of a Migration Console where you perform the migration.

The ZENworks Asset Management Migration utility allows you to migrate the following:

- ♦ Local products
- ♦ Enterprise inventory

1.1 Before You Begin

Before you begin migrating data from ZENworks Asset Management 7.5 to ZENworks 10 Configuration Management, consider the following:

- ♦ You should back up both source and destination databases.
- ♦ Do not use version 10 of the migration utility if you plan on migrating asset management data to ZENworks 10.x Configuration/Asset Management at a later date. If you use version 10 of the ZENworks Asset Management Migration utility, you will not be able to use the upcoming release of the migration utility (version 10.1), which will support migration of asset management data.
- ♦ Workstations must be migrated before the Adaptive Agent is deployed.

To ensure migrated devices are reconciled to active devices in your ZENworks Configuration Management system, first apply System Update 2 (coming soon), migrate devices, and then deploy the ZENworks Configuration Management Adaptive Agent to those devices from the Discovered Devices tab in ZENworks Control Center (under the *Devices created via ZENworks Asset Management Migration* list.)

If you wish to roll out ZENworks Configuration Management in stages, you can still ensure that migrated device inventory is reconciled to active devices in ZENworks Configuration Management by migrating sets of workstations from ZENworks Asset Management and then deploying the Adaptive Agent to those devices using the method described above.

- ♦ You can only migrate objects once.
- ♦ Network devices are not migrated.
- ♦ Custom reports are not migrated.
- ♦ User-defined field data is not migrated.

Using the Novell ZENworks Asset Management Migration Utility

2

The following sections provide instructions on how to use the ZENworks® Asset Management Migration utility to migrate data from ZENworks Asset Management 7.5 to ZENworks 10 Configuration Management:

- ♦ [Section 2.1, “Overview,” on page 11](#)
- ♦ [Section 2.2, “Installing the ZENworks Asset Management Migration Utility,” on page 11](#)
- ♦ [Section 2.3, “Selecting the Migration Source,” on page 12](#)
- ♦ [Section 2.4, “Selecting the Migration Destination,” on page 12](#)
- ♦ [Section 2.5, “Using the Migration Console to Migrate Objects,” on page 13](#)

2.1 Overview

The ZENworks Asset Management Migration utility is used to migrate the following data to ZENworks Configuration Management:

- ♦ **Local Product Definitions:** Local product definitions that were defined in ZENworks Asset Management. You can choose to migrate some or all of these product definitions. For more information, see [Section 2.5.2, “Migrating Local Product Definitions,” on page 13](#).
- ♦ **Inventory:** Inventory data defined by your ZENworks Asset Management collection domains. You can migrate devices individually or as a group. You can also migrate deleted workstations, which are devices that have been deleted in ZENworks Asset Management. For more information, see [Section 2.5.1, “Migrating Inventory Data,” on page 13](#).

Migrating an object is a four-step process:

1. Select the migration source. For more information, see [Section 2.3, “Selecting the Migration Source,” on page 12](#).
2. Select the migration destination. For more information, see [Section 2.4, “Selecting the Migration Destination,” on page 12](#).
3. Select objects to migrate. For more information, see [Section 2.5, “Using the Migration Console to Migrate Objects,” on page 13](#).
4. Initiate the migration. For more information, see [Section 2.5, “Using the Migration Console to Migrate Objects,” on page 13](#).

2.2 Installing the ZENworks Asset Management Migration Utility

- 1 In your web browser, access the following URL:

`http://zenworks_primary_server_id/zenworks-setup/tools/`

- 2 Run `ZAMmigration.exe` to install it on your workstation.

- 3 To run the utility on a supported Windows device, click *Start > All Programs > ZENworks Configuration Management Migration Utility > ZAM Migration Utility*.

2.3 Selecting the Migration Source

The migration source is your ZENworks Asset Management 7.5 database. To log in to your database:

- 1 Click *Start > All Programs > ZENworks Configuration Management Migration Utility > ZAM Migration Utility*.
- 2 Click the button to the right of the *Select ZAM Database* field.
- 3 Fill in the following fields:

Database Type: Specify *MS SQL Server 2000/2005* for both external and embedded MS SQL Server databases.

Database Server: Specify either the DNS name or IP address of the database server. Each time you use this dialog box, the last server you logged in to is displayed here.

Database: Specify the database name. Each time you use this dialog box, the last database you logged in to is displayed here.

User Name: Specify the username. Each time you use this dialog box, the last username you used is displayed here.

Password: Specify the password. This must be specified every time to authenticate.

- 4 Click *OK* to connect. You can click *Test Connection* first to verify that you can connect to the database.
- 5 Continue with [Section 2.4, “Selecting the Migration Destination,” on page 12](#).

2.4 Selecting the Migration Destination

To log in to your migration source Novell® ZENworks Configuration Management Management Zone:

- 1 In the Migration Console, click the button to the right of the *Select Zone* field.
- 2 Fill in the following fields to authenticate to your destination Management Zone:

Zone: Specify your Management Zone. This field is not filled in the first time you access the *Zone Login* dialog box. Thereafter, any zone that you previously logged in to by using this dialog box is available from the drop-down list. Each time you use this dialog box, the last zone that you logged in to is displayed here.

User Name: Specify the username for the zone. *Administrator* is normally used. If this is the first time you have logged in to this zone by using the Migration Console, nothing is displayed; otherwise, the last username you used is displayed. If you select a Management Zone in the *Zone* field, this field is automatically populated with the username you last used for that zone.

Password: Specify the password. This must be entered every time to authenticate.

Primary Server: Specify either its DNS name or IP address. This field is automatically populated when you select a Management Zone in the *Zone* field.

- 3 Click *OK*.

The *Select Objects To Migrate* tab shows the object groups available to migrate along with the number of objects in each group.

- 4 Continue with [Section 2.5, “Using the Migration Console to Migrate Objects,”](#) on page 13.

2.5 Using the Migration Console to Migrate Objects

This section shows you how to migrate objects in each data group. Although the steps to migrate different types of objects are presented separately, it isn't necessary to migrate one type of object at a time. This section includes the following topics:

- ♦ [Section 2.5.1, “Migrating Inventory Data,”](#) on page 13
- ♦ [Section 2.5.2, “Migrating Local Product Definitions,”](#) on page 13

2.5.1 Migrating Inventory Data

- 1 Click *Start > All Programs > ZENworks Configuration Management Migration Utility > ZAM Migration Utility*.
- 2 Log in to your ZENworks Asset Management 7.5 database and the Novell ZENworks Configuration Management Management Zone as shown in [Section 2.3, “Selecting the Migration Source,”](#) on page 12 and [Section 2.4, “Selecting the Migration Destination,”](#) on page 12.
- 3 Click the *Select Objects To Migrate* tab.
- 4 Click *Inventory* and select the desired collection domain and collection server, or click *Deleted Workstations*.

A list of workstations is shown on the right.

- 5 Select the data to migrate.
 - ♦ To select all of the enterprise data, right-click *Enterprise* and select *Migrate All Inventory Data*.
 - ♦ To select individual workstations, right-click a workstation listed on the right side of the panel and select *Add Item(s) To Migration Queue*. You can Shift+click or Ctrl+click to select more than one item.
- 6 (Optional) To remove workstations from the migration list, click the *Items to Migrate* tab, then right-click the workstation and select *Remove Item(s) from Migration Queue*.
- 7 Click *Start Migration*.

The *Migration Status* tab opens and displays the migration details. Migrated workstations appear as discovered devices in ZENworks Control Center.

2.5.2 Migrating Local Product Definitions

- 1 Click *Start > All Programs > ZENworks Configuration Management Migration Utility > ZAM Migration Utility*.
- 2 Click the *Select Objects To Migrate* tab.
- 3 Click *Local Products*.

A list of the local products is shown on the right side of the panel.

4 Select the local products to migrate.

- ♦ To select all of the local products, right-click *Local Products* and select *Migrate All Local Products*.
- ♦ To select individual local products, right-click a local product listed on the right side of the panel and select *Add Item(s) To Migration Queue*.

You can Shift-click or Ctrl-click to select more than one item.

5 (Optional) To remove local products from the migration list, click *Items to Migrate*, then right-click the local product and select *Remove Item(s) from Migration Queue*.

6 Click *Start Migration*.

The *Migration Status* tab opens and displays the migration details.

Understanding the Migration Console

3

The following sections describe the Migration Console and how to use it:

- ♦ [Section 3.1, “Select Objects to Migrate Tab,” on page 15](#)
- ♦ [Section 3.2, “Items to Migrate Tab,” on page 15](#)
- ♦ [Section 3.3, “Migration Status Tab,” on page 16](#)
- ♦ [Section 3.4, “Migration History Tab,” on page 16](#)
- ♦ [Section 3.5, “Migrated Objects Tab,” on page 16](#)
- ♦ [Section 3.6, “Select ZAM Database Field,” on page 16](#)
- ♦ [Section 3.7, “Select Zone Field,” on page 16](#)
- ♦ [Section 3.8, “Start Migration Button,” on page 17](#)
- ♦ [Section 3.9, “Cancel Button,” on page 17](#)

3.1 Select Objects to Migrate Tab

Click the Select Objects to Migrate tab to display the Select Objects to Migrate panel, which shows the three groups of objects you can migrate and indicates how many objects are in each group.

- ♦ **User-Defined Fields:** Custom fields defined in ZENworks Asset Management 7.5. Use these objects to migrate the user-defined field definitions. Only the definitions are migrated, not the field contents. User-defined field contents are migrated when you migrate inventory data.
- ♦ **Local Products:** Software products created and identified to be tracked as part of your inventory. Use these objects to migrate the local product definitions. As with user-defined fields, only the definitions are migrated, not the inventory data.
- ♦ **Inventory:** Inventory data for the enterprise. Use these objects to migrate inventory data.

Click any group to display the objects in that group in the panel on the right, along with additional information depending on the group:

- ♦ For user-defined fields, the *Label*, *Class*, and *DataType* are displayed.
- ♦ For local products, the *Name*, *Manufacturer*, *Version*, *Type*, *Source*, and the *Migrated Date* are displayed.
- ♦ For workstations or the entire enterprise, the *Name*, *Inventory Type*, *Migrated Date*, and *Unique Identifier* are displayed.

3.2 Items to Migrate Tab

The *Items to Migrate* tab shows the name, object type, and the unique identifier of each selected object. Right-click an object and select *Remove Item(s) from Migration Queue* to remove it from the migration list.

3.3 Migration Status Tab

When you migrate an object, you are automatically taken to the *Migration Status* tab, which shows the progress and details of the migration.

3.4 Migration History Tab

The Migration History panel shows what objects have been migrated, along with the object type, status, and migration date. To see the detailed status of a specific migrated object, right-click the object and select *Detailed Status*. The Migration Status panel opens with details about the migration.


3.5 Migrated Objects Tab

The *Migrated Objects* tab shows the objects that have been successfully migrated, including the object type, migrated date, and the object's unique identifier.

3.6 Select ZAM Database Field

The *Select ZAM Database* field shows your source database, which is your ZENworks Asset Management 7.5 database. Click the button to the right of the field to open the *ZAM Database Login* dialog box, where you can log in to your source database.


Figure 3-1 ZAM Database Login

The image shows a Windows-style dialog box titled "ZAM Database Login". The title bar is blue with a close button (X) on the right. The dialog has a light beige background. At the top, there is a header area with the Novell ZENworks logo on the left and a red "N" logo on the right. Below the header, the text "ZENworks Asset Management Migration Utility" is displayed. The main area contains several input fields: "Database Type:" with a dropdown menu showing "MS SQL Server 2000/2005"; "Database Server:" with a text input field; "Database:" with a text input field; "User Name:" with a text input field; and "Password:" with a text input field. At the bottom, there are four buttons: "Test Connection", "Help", "OK", and "Cancel".

3.7 Select Zone Field

The *Select Zone* field shows the migration destination, which is your Novell ZENworks Configuration Management Management Zone. Click the button to the right of the field to open the *Zone Login* dialog box, where you can log in to your destination database.

Figure 3-2 *Zone Login*



Zone Login

Novell ZENworks

ZENworks Asset Management Migration Utility

Zone:
PMRPATCH_ZONE

User Name:
Administrator

Password:

Primary Server:
164.99.114.33

Help OK Cancel

3.8 Start Migration Button

After you select the objects you want to migrate, click *Start Migration* to begin the migration process.

3.9 Cancel Button

The *Cancel* button stops the migration process at the point when you click it. Objects that have already migrated when the *Cancel* button is clicked are not rolled back.